

Chart Display Options (Bar Styles, Sessions, Countdown)

Charts & Workspace | intermediate | 5 min read | DeepCharts Help Center | August 24, 2026

The fastest way to change how a chart looks in DeepCharts is the two-candle icon at the top left of every chart window. Its dropdown holds the bar style (candlestick, line, OHLC), two visual modifiers that encode volume and delta into the candles, the ETH/RTH session switch, the auction filter, the bar-values readout and the bar-close countdown.

Several of these toggles are shortcuts to settings that also live in the **Price Settings** dialog — this article tells you which, so you always know where the "real" setting is. For the full dialog, see Price Chart Settings.

What it is

The bar style dropdown is the chart's quick display menu. It answers "how do I switch to a line chart", "why are my candles different widths or strange colors", "how do I hide overnight data", and "how do I get a countdown to the bar close" — all without opening a settings dialog.

[SCREENSHOT PLACEHOLDER] The two-candle icon dropdown open on a chart, showing Candlestick highlighted as active, Line, OHLC, the Equi-Volume Bars and Delta-Volume Bars checkboxes, ETH Session checked, Auction filter, Bar values checked, Countdown timer, and the Price Settings entry at the bottom `dc-en-chart-display-options-01.png`

When to use it

- Switch between candlestick, line and OHLC rendering.
- Turn on volume-width candles (Equi-Volume) or delta-colored candles (Delta-Volume).
- Show only Regular Trading Hours, or the full ETH session including overnight.
- Toggle the top-left OHLC readout and the bar-close countdown.
- Jump into the full **Price Settings** dialog.

Quick start

1. Click the two-candle icon at the top left of the chart.
2. Pick a base style: **Candlestick** (default), **Line** or **OHLC** — these are exclusive, and the active one is highlighted.
3. Optionally tick **Equi-Volume Bars** and/or **Delta-Volume Bars** — these are checkboxes layered on top of the base style, and both can be on at once.
4. The chart redraws immediately (the auction filter is the one item that triggers a full rebuild).

How to read it

Equi-Volume candles: width encodes the bar's volume relative to other candles — a wide candle traded a lot, a thin one very little. The point is to see instantly whether a big move had real volume behind it or whether a thin book let a small aggressive order move price a long way — judging that mentally from a volume histogram in real time is hard.

Delta-Volume candles: color intensity encodes delta. Pale color = low delta; intense color = high delta. Darker green = more aggressive buyers (positive delta); darker red = more aggressive sellers (negative delta). New to delta? Start with Orderflow 101: Bid, Ask, Aggressor and Delta.

Bar values readout: the top-left **O: H: L: C:** fields plus **%V** (percent change from the previous day's close), **ΣV** and **ΔV** (the bar's volume figures [**CONFIRM: exact definitions of ΣV and ΔV**]). Values populate for the hovered bar, or the last bar when the cursor is off the chart.

New to reading O, H, L and C on a candle? Hover the candle below — each zone explains itself, and you can flip it between bull and bear.

[WIDGET: candle-anatomy]

[SCREENSHOT PLACEHOLDER] Side-by-side comparison of the same price move as standard candlesticks vs with Equi-Volume + Delta-Volume enabled, showing variable candle widths and green/purple intensity differences

dc-en-chart-display-options-02.png

Settings reference

Items in the order they appear in the dropdown:

Item	What it does
Candlestick	Standard candles. Default base style.
Line	A continuous line connecting the closing prices of each candle.
OHLC	Open/high/low/close bars — vertical bars with open and close ticks.
Equi-Volume Bars	Checkbox modifier: candle width = traded volume. Shortcut to Price Settings → VOLUME → Width based volume (same setting, two places).
Delta-Volume Bars	Checkbox modifier: candle color intensity = delta. Shortcut to Price Settings → DELTA → Color based on delta . Can be combined with Equi-Volume.
ETH Session	Default on: the chart shows full Electronic Trading Hours including overnight. Off: ETH bars are hidden and only Regular Trading Hours price action shows. Inverse of Price Settings → DATA → RTH - only (same switch).
Auction filter	Default off. Removes opening/closing auction data from the calculations — exact behavior may vary [CONFIRM: precisely which auction prints are excluded] . Same setting as Price Settings → Exclude Auction (Tick Data) . Toggling it rebuilds the whole chart.
Bar values	Default on. Shows/hides the top-left readout (O H L C, %V, ΣV, ΔV).
Countdown timer	Shows a 00:00 box counting down to the current candle's close, at the bottom of the price scale (a 5-minute chart counts down 5 minutes per candle). The box position is configurable in Price Settings → COUNTDOWN: Axis mode pins it to the scale, Floating mode makes it a free box you can drag anywhere.
■ Price Settings	Opens the full Price Settings dialog — see Price Chart Settings.

Note: Toggling **Auction filter** shows the **Building chart** spinner while the whole chart rebuilds. The short wait is normal — nothing is broken.

Related display controls elsewhere

- **Bar type and timeframe** (minutes, Range, Renko, Volume, Delta bars...) are chosen in the title-bar timeframe dropdown or **Price Settings** → **Param Type** — see Price Chart Settings.
- **Custom session windows** (e.g. only the first two hours after the open) and the vertical day-start line are configured in **Price Settings** → **CUSTOM TIME SESSION** and **LINE START DAY**.
- Chart background, grid and text colors live in right-click → **Properties** — see The Chart Window.

Tips and common mistakes

- **"My candles look washed out / the colors are strange"** — Delta-Volume mode is on. Intensity encodes delta; it is not a broken theme. Untick **Delta-Volume Bars** to go back.
- **"My candles have different widths"** — Equi-Volume mode is on; width encodes volume.
- **"My chart shows different candles than my colleague's"** — check the **ETH Session** toggle first: one of you is likely on RTH-only. Session basics: Understanding Market Structure and Sessions (RTH/ETH, Rollover).
- **"The countdown sits at 00:00"** — on a delayed or idle feed there are no live ticks driving it; see Use the Free 15-Minute Delayed Data Feed.
- **"My OHLC readout is empty"** — the fields only populate while hovering bars (or from the last bar); if they never populate, check that **Bar values** is ticked.
- The two checkbox modifiers and the base styles are independent: switching Candlestick → Line keeps Equi-Volume/Delta-Volume ticked.

Related articles

- Price Chart Settings
- The Chart Window
- Understanding Market Structure and Sessions (RTH/ETH, Rollover)
- Orderflow 101: Bid, Ask, Aggressor and Delta
- Quick Chart Templates (OF-VP, D-VP, W-VP...)