

On Candle Stats

Indicators & Analysis / Volume & Delta | intermediate | 4 min read | DeepCharts Help Center | July 15, 2026

On Candle Stats prints detailed statistics directly on your candles as text boxes: total volume, delta, trade counts, and other market microstructure data, bar by bar. Instead of glancing between the chart and a separate panel, the numbers sit right next to the price action they describe.

It is a favorite for orderflow traders who want footprint-grade information at a glance without opening a full footprint chart for every instrument.

What it is

For each candle, the indicator computes a set of data series — eleven are available, including Max/Min Delta, total volume, delta volume, total trades, delta trades, extension, COT High, COT Low, COT Bar, Bid-Ask/Vol, and Ratio — and renders your chosen values as a compact text box positioned above, below, or on the candle. Coloring and opacity options tie the text's appearance to delta sign and magnitude, so the annotation itself carries a directional read

[SCREENSHOT PLACEHOLDER] Chart with On Candle Stats active — small text boxes above each candle showing volume and delta values, positive-delta candles labeled in green text and negative in red
on-candle-stats-chart-overview.png

When to use it

- You want exact per-bar numbers (volume, delta, trades) visible on the chart while you trade.
- You review sessions bar by bar and need microstructure detail without switching to Deep Print (Footprint).
- You compare aggression across consecutive candles at key levels — for example delta shrinking as price presses into resistance.
- You annotate charts for journaling or teaching, where the values must be readable in a screenshot.

Quick start

1. Open the **Indicator List** on your chart and add **On Candle Stats**.
2. Open the indicator's **Settings**.
3. Keep **Input Data** on **Volume** to start; switch to **Aggregate Volume** when you want orders at the same price combined for a more accurate activity view (see Different Types of Input Data for Indicators).
4. Enable the subgraph series you actually need — **Tot. Vol** and **Delta Vol** are a good minimal pair — and leave the rest off to keep the chart legible.
5. Turn on **Color Text Based on Delta** so positive readings print in one color (typically green) and negative in another (typically red).
6. Set **Price Plot** to **High** and add a small **Tick Offset** so text boxes sit clear of the candle wicks.

[SCREENSHOT PLACEHOLDER] On Candle Stats settings dialog — Data Settings at top (Input Data, Filter Min, Filter Max), with Text, Coloring and Price sections below, Color Text Based on Delta enabled
on-candle-stats-settings-dialog.png

How to read it

- **Volume with delta context** — a high-volume candle with small delta means two-sided battle; high volume with strongly one-sided delta means conviction.

- **Delta against the candle's direction** — a green candle printing negative delta (or vice versa) hints at absorption or passive strength; worth a closer look on a footprint.
- **Trade counts vs. volume** — many trades with modest volume suggests small participants; fewer trades carrying big volume suggests size is active.
- **Opacity grading** — with **Opacity Based on Ratio** enabled, fainter boxes mark statistically ordinary bars and stronger boxes mark the ones that deviate, letting you skim a session quickly.

Settings reference

Data Settings

Setting	What it does
Input Data	Database used for the statistics: Volume (total volume at each price level — trading intensity), Order (transaction count at each price level — order frequency), or Aggregate Volume (combines orders at the same price level for a more accurate activity view).
Filter Min	Minimum threshold — only data above this value is displayed.
Filter Max	Maximum threshold — set to 0 to apply no maximum filter.

Text Settings

Setting	What it does
Font Size	Text size on the candles.
Smaller Font Size	Minimum text size kept for readability at smaller chart scales.
Auto Text Format	When enabled, numbers above a thousand display grouped (e.g., "1,234").
Absolute Sign	When enabled, values display without +/- signs.

Coloring Settings

Setting	What it does
Opacity Based on Ratio	Adjusts text-box opacity according to the bar's ratio, de-emphasizing ordinary bars.
Max Ratio	Controls the maximum opacity ratio and text-box visibility.
Color Text Based on Delta	Positive delta prints in one color (typically green), negative delta in another (typically red).

Price Settings

Setting	What it does
Tick Offset	Distance in ticks between the text box and the candle, preventing overlap with price action.
Price Plot	Text placement: High , Low , Center , Price Slope , or Delta Sign .

Subgraphs

Eleven data series are available to display: **Max/Min Delta**, **Tot. Vol**, **Delta Vol**, **Tot. Trade**, **Delta Trade**, **Extension**, **COT High**, **COT Low**, **COT Bar**, **Bid-Ask/Vol**, and **Ratio**. Enable only the series you read — each active series adds a line of text to every candle.

Tips and common mistakes

- **Less is more.** Enabling many subgraph series turns every candle into a paragraph. Two or three well-chosen values beat eleven unread ones.
- **Mind the zoom level.** Text needs horizontal room; on tightly zoomed-out charts enable **Smaller Font Size** or the boxes will collide.
- **Delta Sign placement is contextual.** Setting **Price Plot** to **Delta Sign** moves the text with the delta's direction, which makes one-glance reading faster but shifts box positions bar to bar — pick it deliberately.
- **Use Absolute Sign for journaling screenshots** where color already carries the sign and the +/- clutter adds nothing.

Related articles

- [Deep Print \(Footprint\)](#)
- [Deep Stats](#)
- [Delta Bar](#)
- [Market Statistics](#)
- [Orderflow 101: Bid, Ask, Aggressor and Delta](#)
- [Different Types of Input Data for Indicators](#)
- [How to Change the Layout of Indicators](#)