

Ismod.c File Reference

Go to the source code of this file.

Kconfigs

ENABLE_FEATURE_2_4_MODULES
ENABLE_FEATURE_CHECK_TAINTED_MODULE
ENABLE_FEATURE_CLEAN_UP
ENABLE_FEATURE_LSMOD_PRETTY_2_6_OUTPUT
ENABLE_UNICODE_SUPPORT

Enumerations

enum	{	TAINT_PROPRIETARY_MODULE	=	(1 << 0)	,	TAINT_FORCED_MODULE	=	(1 << 1)	,	TAINT_UNSAFE_SMP	=	(1 << 2)	}
------	---	--------------------------	---	----------	---	---------------------	---	----------	---	------------------	---	----------	---

Functions

static void	check_tainted	(void)
int	Ismod_main	(int argc, char **argv) MAIN_EXTERNALLY_VISIBLE
int	Ismod_main	(int argc UNUSED_PARAM, char **argv UNUSED_PARAM)

Kconfig Documentation

- ◆ ENABLE_FEATURE_2_4_MODULES

Name: FEATURE_2_4_MODULES

Type: bool

Default: 0 if (INSMOD || RMMOD || LSMOD)

Prompt: "Support version 2.2/2.4 Linux kernels" if (INSMOD || RMMOD || LSMOD)

Depends on: (INSMOD || RMMOD || LSMOD)

Help:

Support module loading for 2.2.x and 2.4.x Linux kernels.
This increases size considerably. Say N unless you plan
to run ancient kernels.

Defined at line 122 of file modutils/Config.in.

Used at line 54 of file [modutils/lsmmod.c](#).

◆ ENABLE_FEATURE_CHECK_TAINTED_MODULE

Name: FEATURE_CHECK_TAINTED_MODULE

Type: bool

Default: 1 if ((LSMOD || FEATURE_2_4_MODULES) && !MODPROBE_SMALL)

Prompt: "Support tainted module checking with new kernels" if ((LSMOD || FEATURE_2_4_MODULES) && !MODPROBE_SMALL)

Depends on: ((LSMOD || FEATURE_2_4_MODULES) && !MODPROBE_SMALL)

Help:

Support checking for tainted modules. These are usually binary
only modules that will make the linux-kernel list ignore your
support request.
This option is required to support GPLONLY modules.

Defined at line 196 of file modutils/Config.in.

Used at line 13 of file [modutils/lsmmod.c](#).

◆ ENABLE_FEATURE_CLEAN_UP

Name: FEATURE_CLEAN_UP

Type: bool

Default: 0

Prompt: "Clean up all memory before exiting (usually not needed)"

Help:

As a size optimization, busybox normally exits without explicitly freeing dynamically allocated memory or closing files. This saves space since the OS will clean up for us, but it can confuse debuggers like valgrind, which report tons of memory and resource leaks.

Don't enable this unless you have a really good reason to clean things up manually.

Defined at line 254 of file Config.in.

Used at lines [26](#) and [94](#) of file [modutils/lsmode.c](#).

◆ ENABLE_FEATURE_LSMODE_PRETTY_2_6_OUTPUT

Name: FEATURE_LSMODE_PRETTY_2_6_OUTPUT

Type: bool

Default: 0 if (LSMOD)

Prompt: "Pretty output" if (LSMOD)

Depends on: (LSMOD)

Help:

This option makes output format of lsmod adjusted to the format of module-init-tools for Linux kernel 2.6.
Increases size somewhat.

Defined at line 83 of file modutils/Config.in.

Used at line [46](#) of file [modutils/lsmode.c](#).

◆ ENABLE_UNICODE_SUPPORT

Name: UNICODE_SUPPORT

Type: bool

Default: 1

Prompt: "Support Unicode"

Help:

This makes various applets aware that one byte is not one character on screen.

Busybox aims to eventually work correctly with Unicode displays.

Any older encodings are not guaranteed to work.

Probably by the time when busybox will be fully Unicode-clean, other encodings will be mainly of historic interest.

Defined at line 122 of file Config.in.

Used at lines [63](#) and [81](#) of file [modutils/lsmmod.c](#).

Enumeration Type Documentation

◆ anonymous enum

anonymous enum

Enumerator	
TAINT_PROPRIETARY_MODULE	
TAINT_FORCED_MODULE	
TAINT_UNSAFE_SMP	

Definition at line [14](#) of file [lsmmod.c](#).

Function Documentation

◆ check_tainted()

```
static void check_tainted ( void )
```

static

Definition at line **20** of file **lsmmod.c**.

◆ lsmmod_main() [1/2]

```
int lsmmod_main ( int argc    UNUSED_PARAM,  
                  char **argv UNUSED_PARAM  
                  )
```

Definition at line **44** of file **lsmmod.c**.

◆ lsmmod_main() [2/2]

```
int lsmmod_main ( int    argc,  
                  char ** argv  
                  )
```