

Bug Report

ID number	#1
Name	Tooltip is displayed outside hover area
Reporter	Yana B.
Submit Date	17/01/2026
Summary	Tooltip appears outside hover area and does not hide correctly in file upload component
URL	https://the-internet.herokuapp.com/upload
Screenshot	<p>The screenshot shows a file upload interface. At the top, there is a text input field with the placeholder "Выберите файл" (Select file) and a tooltip "Файл не выбран" (File not selected). Below the input is a blue "Upload" button. A large red dashed rectangle highlights a specific area of the interface. In the bottom right corner of the page, there is another tooltip "Test the herokuApp upload file page.docx".</p>
Platform	Macintosh
Operating System	Tahoe 26.1, 25B78
Browser	Chrome 144.0.7559.59
Severity	Minor

Assigned to	/
Priority	Low

Description

The tooltip in the file upload component is sometimes displayed outside the hover area and does not hide correctly when the cursor moves away.

This issue occurs in different states:

No file selected: the tooltip «No file selected» remains visible after selecting a file and moving the cursor away from the Select a file button.

After clearing a selected file: the tooltip showing the name of the previously selected (now removed) file remains visible after moving the cursor away from the Select a file button.

Steps to reproduce

Scenario 1 - «No file selected»:

- > click on «Select a file»
- > Select a file
- > move the cursor away from the button

Scenario 2 - after clearing a selected file:

- > click on «Select a file»
- > select a file
- > remove the selected file (click «Cancel» in the file picker)
- > move the cursor away from the button

Expected result

The tooltip appears only when hovering over the file upload button or file name and disappears immediately when the cursor leaves the hover area.

Scenario 1: the tooltip with a file name is displayed when the cursor hovers the «Select a file» button or a file name, and disappears immediately when the cursor leaves the hover area.

Scenario 2: the tooltip «No file selected» is displayed when the cursor hovers the «Select a file» button.

Actual result

Scenario 1: the tooltip «No file selected» remains visible at the hover area and outside the hover area

Scenario 2: the tooltip with the name of the deleted file remains visible at the hover area and outside the hover area