



navya@kali: ~

Session Actions Edit View Help

(navya@kali)-[~]

\$ sudo apt update

[sudo] password for navya:

Get:1 http://kali.download/kali kali-rolling InRelease [34.0 kB]

Get:2 http://kali.download/kali kali-rolling/main amd64 Packages [21.3 MB]

Get:3 http://kali.download/kali kali-rolling/main amd64 Contents (deb) [53.5 MB]

Get:4 http://kali.download/kali kali-rolling/contrib amd64 Packages [102 kB]

Get:5 http://kali.download/kali kali-rolling/contrib amd64 Contents (deb) [188 kB]

Get:6 http://kali.download/kali kali-rolling/non-free amd64 Packages [169 kB]

Get:7 http://kali.download/kali kali-rolling/non-free amd64 Contents (deb) [887 kB]

Get:8 http://kali.download/kali kali-rolling/non-free-firmware amd64 Packages [15.4 kB]

Get:9 http://kali.download/kali kali-rolling/non-free-firmware amd64 Contents (deb) [40.1 kB]

Fetch: 76.3 MB in 25s (3,005 kB/s)

617 packages can be upgraded. Run 'apt list --upgradable' to see them.

(navya@kali)-[~]

\$ sudo apt upgrade -y





navya@kali: ~

Session Actions Edit View Help

```
(navya@kali)~  
$ uname -r  
6.19.14+kali-amd64  
  
(navya@kali)~  
$ sudo ufw enable  
[sudo] password for navya:  
sudo: ufw: command not found  
  
(navya@kali)~  
$ sudo apt install ufw -y  
The following packages were automatically installed and are no longer required:  
  firmware-marvell-presteria libvidstab1.1 linux-base-6.18.12+kali-amd64 linux-image-6.18.12+kali-amd64 node-jsbn  
Use 'sudo apt autoremove' to remove them.  
  
Installing:  
  ufw  
  
Suggested packages:  
  rsyslog  
  
Summary:  
  Upgrading: 0, Installing: 1, Removing: 0, Not Upgrading: 61  
  Download size: 169 kB  
  Space needed: 880 kB / 22.4 GB available  
  
Get:1 http://kali.download/kali kali-rolling/main amd64 ufw all 0.36.2-9 [169 kB]  
Fetched 169 kB in 1s (259 kB/s)
```

Session Actions Edit View Help

No VM guests are running outdated hypervisor (qemu) binaries on this host.

```
(navya@kali)-[~]
$ sudo ufw enable
Firewall is active and enabled on system startup
```

```
(navya@kali)-[~]
$ sudo ufw default deny incoming
Default incoming policy changed to 'deny'
(be sure to update your rules accordingly)
```

```
(navya@kali)-[~]
$ sudo ufw default allow outgoing
Default outgoing policy changed to 'allow'
(be sure to update your rules accordingly)
```

```
(navya@kali)-[~]
$ sudo ufw allow ssh
Rule added
Rule added (v6)
```

```
(navya@kali)-[~]
$ sudo ufw status verbose
Status: active
Logging: on (low)
Default: deny (incoming), allow (outgoing), deny (routed)
New profiles: skip
```

To	Action	From
--	--	--
22/tcp	ALLOW IN	Anywhere
22/tcp (v6)	ALLOW IN	Anywhere (v6)

```
(navya@kali)-[~]
$
```

Session Actions Edit View Help

Logging: on (low)
Default: deny (incoming), allow (outgoing), deny (routed)
New profiles: skip

To	Action	From
--		
22/tcp	ALLOW IN	Anywhere
22/tcp (v6)	ALLOW IN	Anywhere (v6)

(navya@kali)-[~]
\$ sudo systemctl list-units --type=service --state=running

UNIT	LOAD	ACTIVE	SUB	DESCRIPTION
accounts-daemon.service	loaded	active	running	Accounts Service
colord.service	loaded	active	running	Manage, Install and Generate Color Profiles
containerd.service	loaded	active	running	containerd container runtime
cron.service	loaded	active	running	Regular background program processing daemon
dbus.service	loaded	active	running	D-Bus System Message Bus
docker.service	loaded	active	running	Docker Application Container Engine
getty@tty1.service	loaded	active	running	Getty on tty1
gsad.service	loaded	active	running	Greenbone Security Assistant daemon (gsad)
gvmd.service	loaded	active	running	Greenbone Vulnerability Manager daemon (gvmd)
haveged.service	loaded	active	running	Entropy Daemon based on the HAVEGE algorithm
lightdm.service	loaded	active	running	Light Display Manager
ModemManager.service	loaded	active	running	Modem Manager
mosquitto.service	loaded	active	running	Mosquitto MQTT Broker
NetworkManager.service	loaded	active	running	Network Manager
notus-scanner.service	loaded	active	running	Notus Scanner
osspd-openvas.service	loaded	active	running	OSPd Wrapper for the OpenVAS Scanner (osspd-openvas)
polkit.service	loaded	active	running	Authorization Manager
postgresql@18-main.service	loaded	active	running	PostgreSQL Cluster 18-main
redis-server@openvas.service	loaded	active	running	Advanced key-value store (openvas)
rtkit-daemon.service	loaded	active	running	RealtimeKit Scheduling Policy Service
strongswan-starter.service	loaded	active	running	strongSwan IPsec IKEv1/IKEv2 daemon using ipsec.conf
systemd-journald.service	loaded	active	running	Journal Service
systemd-logind.service	loaded	active	running	User Login Management
systemd-udevd.service	loaded	active	running	Rule-based Manager for Device Events and Files
systemd-userdbd.service	loaded	active	running	User Database Manager
udisks2.service	loaded	active	running	Disk Manager
upower.service	loaded	active	running	Daemon for power management
user@1000.service	loaded	active	running	User Manager for UID 1000
virtualbox-guest-utils.service	loaded	active	running	Virtualbox guest utils

Legend: LOAD → Reflects whether the unit definition was properly loaded.
ACTIVE → The high-level unit activation state, i.e. generalization of SUB.
SUB → The low-level unit activation state, values depend on unit type.

29 loaded units listed.

(navya@kali)-[~]
\$



navya@kali: ~

Session Actions Edit View Help

osspd-openvas.service	loaded active running	OSPD Wrapper for the OpenVAS Scanner (ospd-openvas)
polkit.service	loaded active running	Authorization Manager
postgresql@18-main.service	loaded active running	PostgreSQL Cluster 18-main
redis-server@openvas.service	loaded active running	Advanced key-value store (openvas)
rtkit-daemon.service	loaded active running	RealtimeKit Scheduling Policy Service
strongswan-starter.service	loaded active running	strongSwan IPsec IKEv1/IKEv2 daemon using ipsec.conf
systemd-journald.service	loaded active running	Journal Service
systemd-logind.service	loaded active running	User Login Management
systemd-udevd.service	loaded active running	Rule-based Manager for Device Events and Files
systemd-userdbd.service	loaded active running	User Database Manager
udisks2.service	loaded active running	Disk Manager
upower.service	loaded active running	Daemon for power management
user@1000.service	loaded active running	User Manager for UID 1000
virtualbox-guest-utils.service	loaded active running	Virtualbox guest utils

Legend: LOAD → Reflects whether the unit definition was properly loaded.
ACTIVE → The high-level unit activation state, i.e. generalization of SUB.
SUB → The low-level unit activation state, values depend on unit type.

29 loaded units listed.

(navya@kali)-[~]

```
$ sudo systemctl stop ModemManager.service
sudo systemctl disable ModemManager.service
```

```
sudo systemctl stop colord.service
sudo systemctl disable colord.service
```

```
sudo systemctl stop mosquito.service
sudo systemctl disable mosquito.service
```

Removed '/etc/systemd/system/dbus-org.freedesktop.ModemManager1.service'.

Removed '/etc/systemd/system/multi-user.target.wants/ModemManager.service'.

The unit files have no installation config (WantedBy=, RequiredBy=, UpheldBy=, Also=, or Alias= settings in the [Install] section, and DefaultInstance= for template units). This means they are not meant to be enabled or disabled using systemctl.

Possible reasons for having these kinds of units are:

- A unit may be statically enabled by being symlinked from another unit's .wants/, .requires/, or .upholds/ directory.
- A unit's purpose may be to act as a helper for some other unit which has a requirement dependency on it.
- A unit may be started when needed via activation (socket, path, timer, D-Bus, udev, scripted systemctl call, ...).
- In case of template units, the unit is meant to be enabled with some instance name specified.

(navya@kali)-[~]

```
$
```



```
Session Actions Edit View Help
upower.service          loaded active running Daemon for power management
user@1000.service       loaded active running User Manager for UID 1000
virtualbox-guest-utils.service loaded active running Virtualbox guest utils

Legend: LOAD    → Reflects whether the unit definition was properly loaded.
          ACTIVE → The high-level unit activation state, i.e. generalization of SUB.
          SUB     → The low-level unit activation state, values depend on unit type.

29 loaded units listed.

(navya@kali)-[~]
$ sudo systemctl stop ModemManager.service
sudo systemctl disable ModemManager.service

sudo systemctl stop colord.service
sudo systemctl disable colord.service

sudo systemctl stop mosquitto.service
sudo systemctl disable mosquitto.service
Removed '/etc/systemd/system/dbus-org.freedesktop.ModemManager1.service'.
Removed '/etc/systemd/system/multi-user.target.wants/ModemManager.service'.
The unit files have no installation config (WantedBy=, RequiredBy=, UpheldBy=,
Also=, or Alias= settings in the [Install] section, and DefaultInstance= for
template units). This means they are not meant to be enabled or disabled using systemctl.

Possible reasons for having these kinds of units are:
• A unit may be statically enabled by being symlinked from another unit's
  .wants/, .requires/, or .upholds/ directory.
• A unit's purpose may be to act as a helper for some other unit which has
  a requirement dependency on it.
• A unit may be started when needed via activation (socket, path, timer,
  D-Bus, udev, scripted systemctl call, ...).
• In case of template units, the unit is meant to be enabled with some
  instance name specified.

(navya@kali)-[~]
$ sudo systemctl list-units --type=service --state=running
UNIT                                LOAD    ACTIVE SUB    DESCRIPTION
accounts-daemon.service             loaded active running Accounts Service
colord.service                      loaded active running Manage, Install and Generate Color Profiles
containerd.service                 loaded active running containerd container runtime
cron.service                       loaded active running Regular background program processing daemon
dbus.service                       loaded active running D-Bus System Message Bus
docker.service                    loaded active running Docker Application Container Engine
getty@tty1.service                 loaded active running Getty on tty1
gsad.service                       loaded active running Greenbone Security Assistant daemon (gsad)
gvmd.service                      loaded active running Greenbone Vulnerability Manager daemon (gvmd)
haveged.service                   loaded active running Entropy Daemon based on the HAVEGE algorithm
lightdm.service                   loaded active running Light Display Manager
mosquitto.service                 loaded active running Mosquitto MQTT Broker
NetworkManager.service             loaded active running Network Manager
```



navya@kali: ~

Session Actions Edit View Help

```
redis-server@openvas.service loaded active running Advanced key-value store (openvas)
rtkit-daemon.service loaded active running RealtimeKit Scheduling Policy Service
strongswan-starter.service loaded active running strongSwan IPsec IKEv1/IKEv2 daemon using ipsec.conf
systemd-journald.service loaded active running Journal Service
systemd-logind.service loaded active running User Login Management
systemd-udevd.service loaded active running Rule-based Manager for Device Events and Files
systemd-userdbd.service loaded active running User Database Manager
udisks2.service loaded active running Disk Manager
upower.service loaded active running Daemon for power management
user@1000.service loaded active running User Manager for UID 1000
virtualbox-guest-utils.service loaded active running Virtualbox guest utils
```

Legend: LOAD → Reflects whether the unit definition was properly loaded.
ACTIVE → The high-level unit activation state, i.e. generalization of SUB.
SUB → The low-level unit activation state, values depend on unit type.

28 loaded units listed.

```
(navya@kali)-[~]
$ sudo systemctl stop colord.service
```

```
(navya@kali)-[~]
$ sudo systemctl status colord.service
```

I

