

GOLDSCALPERNINJA EA V3.0 - USER MANUAL

VERSION: V3.0



I. EXECUTIVE OVERVIEW & CORE LOGIC

GoldScalperNinja is a highly advanced automated trading system engineered to adapt to volatile market conditions. It moves away from traditional, rigid martingale strategies by incorporating a dynamic grid approach combined with an intelligent recovery system.

Instead of waiting for a massive market reversal to close a heavily drawn-down grid, the EA utilizes a **Smart Sequence Pruning** mechanism. When the market moves against the initial positions, the EA locks in profits from newly opened, advantageous trades and uses that exact profit to quietly trim and close the oldest, most negative trades in the background. This "rolling" recovery method continuously shrinks the grid size, frees up margin, and drastically reduces account drawdown without requiring a full market reversal.



II. THE "TREND MASTER" SYSTEM (D1)

The core directional filter of the EA is the proprietary **Trend Master** module. It does not rely on lagging standard indicators. Instead, it operates on the Daily (D1) timeframe, analyzing the true momentum of the previous day by calculating the specific weight of the candle's body versus its wick, combined with the Average True Range (ATR).

At the start of each day, Trend Master projects a dynamic "Control Zone" (Upper and Lower limits). Throughout the day, the EA tracks the real-time price percentage within this zone. If the price breaks the upper limit, the EA locks into an **Uptrend** bias (restricting sell entries). If it breaks the lower limit, it locks into a **Downtrend** bias (restricting buy entries). If it remains inside, it identifies a **Sideway** market, allowing dual-directional trading. This ensures the EA always trades in harmony with the actual daily institutional flow.



How to Calculate Upper/Lower Limit Lines

- **Step 1** — Calculate yesterday's candlestick volatility (Z-value):

Taking the Candlestick Body ($|Close - Open|$) $\times$ Candlestick Body Weights + Candlesticks $\times$ Candlestick Weights. These two parameters default to 0.7 and 0.3, which means that the candlestick body takes precedence over the beard.

- **Step 2** — Calculate the N-Day Average ATR:

Calculate the True Range for each day in the last N days (default 14 days), taking the average of the additions. This is a measure of the average daily volatility.

- **Step 3** — Calculate the A-value (breakout threshold):

$A = \max(Z \times 0.5, ATR \times \text{Minimum ATR Factor})$. Make sure the threshold is not too small even if the market is very quiet.

- **Step 4** — Determine the Upper/Lower Limit:

Upper Limit = Today's D1 opening price + A-value. Lower Limit = D1 opening price today - A-value. These two lines are plotted on the chart by horizontal lines in green (Upper) and red (Lower), with a white dotted line representing the Open D1 level.



Trend Classification

Price Placement	Status	Meaning
Price > Upper Limit	TREND UP	The bullish momentum is dominating
Price < Lower Limit	TREND DOWN	The downward momentum is dominating
Lower $\leq$ Upper Price	SIDEWAY	Markets in the Balance Zone



In addition, the bot also calculates the % of the price position in the Lower $\rightarrow$ Upper band (called the % zone). For example, 0% = close to Lower, 100% = close to Upper, 50% = center.





How Trend Masters Affect Trading

Depending on the command-oriented mode (Command-oriented mode) you choose:

Modes	Behavior
BUY Only	The bot only opens BUY orders, ignoring any SELL signals
SELL Only	The bot only opens SELL orders, ignoring any BUY signals
Both BUY and SELL	Two-way free, no trend filtering
Auto Follow Trend Master	The bot reads the status of D1 and % of the area to grant/lock the right to open the order

When Trend Master Auto mode is enabled, two important parameters are:

1. Above this % → BUY priority (default 75%): When the price $\geq$ 75% of the locked → zone open a new SELL order
2. Below this % → prioritize SELL (default 25%): When the price $\leq$ 25% of the locked → open a new BUY order

Note: The DCA of the old command STILL continues to run normally. Only the first order of the new chain is locked.



III. DETAILED PARAMETER SETTINGS

Below is the complete list of inputs exactly as they appear in your EA's settings panel.

ORDER DIRECTION / TREND FILTER

- **Allow entries in trend direction**

When enabled, the EA is permitted to open additional grid trades in the direction of the current trend (e.g., buying higher highs or selling lower lows) to maximize trending momentum.

- **Trade direction mode**

The master control for the bot's trading behavior. You can force it to "Only BUY", "Only SELL", "BUY & SELL" (Hedging), or set it to "Auto Trend Master" where it decides the direction based on the D1 momentum logic.

- **Global permission to open BUY**

A strict true/false toggle. If false, the EA will absolutely not open any new BUY sequences under any circumstances.

- **Global permission to open SELL**

A strict true/false toggle. If false, the EA will absolutely not open any new SELL sequences under any circumstances.

- **Above this % → prefer BUY (0-100)**

The specific percentage threshold within the Trend Master zone. If the current price location exceeds this percentage, the EA will heavily prioritize or restrict trading to the BUY direction.

- **Below this % → prefer SELL (0-100)**

The specific percentage threshold within the Trend Master zone. If the current price location drops below this percentage, the EA will heavily prioritize or restrict trading to the SELL direction.

ENTRY & GRID SETTINGS

- **Entry mode**

The execution style for the grid. Can be set to standard Stop orders, StopLimit orders, or Virtual Stop (which hides pending levels from the broker and executes via market orders

when the price is hit).

- **First grid step (points)**

The required price distance from the current market price to the very first pending order of the grid.

- **Minimum distance between orders (points)**

The absolute minimum price gap allowed between any two averaging orders in the sequence.

- **Grid step (points)**

The standard distance interval for placing consecutive grid orders.

- **Min distance after MaxTrade (points)**

A wider minimum distance applied only after the grid has expanded beyond a certain number of trades, used to stretch the grid during strong trends.

- **Grid step after MaxTrade (points)**

The expanded grid step applied after the trade count threshold is reached.

- **Threshold before switching to Step1**

The exact number of open trades required to trigger the wider "Step1" and "Min distance after MaxTrade" settings.

- **Trail pending orders by price (points)**

The distance used to dynamically drag and modify pending orders so they follow the current market price.

- **Orders per grid level**

How many separate trades the EA is allowed to open at one specific grid price level.

- **Initial lot size**

The starting volume for the very first trade of any sequence.

- **Additive lot multiplier**

A fixed amount of volume added to the lot size of subsequent grid orders (e.g., +0.01 per level).

- **Exponential lot multiplier**

The martingale coefficient. The previous lot size is multiplied by this value to aggressively average the entry price.

- **Orders per tier (lot step levels)**

How many consecutive trades must be opened before the lot multiplier (Additive or Exponential) is applied.

- **Enable per-order lot cap**

If true, the EA will never open a single trade larger than the limit defined below.

- **Max lot per single order**

The absolute maximum volume allowed for one individual trade, preventing excessively large positions deep in the grid.

- **Enable total lot cap**

If true, the EA monitors the combined volume of all open trades.

- **Max total lot (both sides)**

The maximum combined volume allowed across all BUY and SELL trades. Once reached, no new trades are opened.

- **Lot precision (decimals)**

Defines the decimal places for lot sizes (usually 2 for 0.01 micro-lots).

- **Enable aggressive mode**

Accelerates the placement and trailing of pending orders, highly effective in fast-moving market sessions.

- **Deviation for virtual stop DEAL**

The maximum allowable slippage (in points) when the EA executes a Virtual Stop via a market order.

TARGET LOSS & TRAILING MANAGEMENT

- **Chain take profit (\$)**

The total net profit target (in deposit currency) required to close an entire grid sequence (all Buys or all Sells) simultaneously.

- **Single-order take profit (\$)**

The individual profit target for the first, standalone trade before the grid expands.

- **Global stop loss (\$)**

The ultimate emergency stop loss. If the floating loss of a sequence hits this currency amount, the EA will close it to prevent a margin call.

- **Trailing mode**

Defines the trailing logic. Set to 0 to disable, 1 for Candle trailing, 2 for Fractal trailing, or >2 to trail by a fixed number of points.

- **Trailing step (points)**

The frequency/interval at which the Stop Loss is moved into profit.

- **Min profit to start trailing (points)**

The trade must be in profit by this many points before the trailing stop initiates.

- **TP distance for first order per side (points)**

A specific take-profit distance applied exclusively to the initial order of a sequence.

- **Trailing timeframe (minutes; 0=chart TF)**

The timeframe used to calculate the highs/lows for Candle or Fractal trailing (e.g., 15 = M15).

- **Activate global SL move & Global SL move distance (points)**

Advanced settings that dynamically shift the break-even or stop-loss point for the entire grid sequence based on the average profit per lot.

ADVANCED MODE (PRUNING & HEDGING)

- **Enable dual-direction trading**

Allows the EA to open Hedging sequences (trading both BUY and SELL simultaneously) to stabilize margin.

- **Open dual-direction every X orders**

The frequency interval for opening a counter-direction sequence while the primary sequence is active.

- **Enable sequence pruning**

The master switch for the Smart Pruning system (using new winning trades to trim old losing trades).

- **Activate when total orders >= this**

The grid must reach this many open trades before the EA starts looking for pruning opportunities.

- **Number of oldest orders to prune from**

How many of the oldest, deepest drawdown trades the EA will target to close during a pruning cycle.

- **Max newest orders to use (0 = auto)**

How many of the most recent, highly profitable trades the EA will sacrifice to offset the losses of the old trades.

- **Minimum profit after pruning (\$)**

The guaranteed net profit (in currency) that must remain in your balance after a pruning cycle completes.

- **Enable cross-side pruning**

If true, the EA can use profits from a winning BUY sequence to trim losses from a trapped SELL sequence (and vice versa), accelerating overall recovery.

- **Min profit after cross pruning (\$)**

The guaranteed net profit required when performing a cross-side (Buy vs. Sell) prune.

CYCLE CONTROL

- **Default cycle state ON/OFF**

If set to ON, the EA will continuously trade, opening a new sequence as soon as the old one closes. If set to OFF, the EA will manage and close the current open trades but will refuse to start any new sequences.

DAILY LIMITS

- **Daily profit target \$ (0=off)**

Your daily profit goal. If this currency amount is reached, the EA notes the target.

- **Daily max loss \$ (0=off)**

Your maximum acceptable daily drawdown limit.

- **Close all when target reached**

If true, the EA will instantly close all open positions the moment the Daily Profit Target is hit, securing your funds.

- **Close all when max loss reached**

If true, the EA will instantly cut all trades if the Daily Max Loss is hit, preventing further damage to the account.

NEWS FILTER SETTINGS

- **Enable news filter**

Activates the internal integration with the MQL5 Economic Calendar to detect high-impact (red folder) news events.

- **Pause before news (minutes)**

The EA will stop opening new initial trades this many minutes before a major news release.

- **Pause after news (minutes)**

The EA will remain paused for this many minutes after the news release to avoid trading the chaotic aftermath.

SAFE CLOSE SETTINGS

- **Enable safe close mode**

Activates a defensive protocol. If the market becomes hostile and the sequence is trapped, the EA will accept a minor loss rather than risking the entire account.

- **Max allowed floating loss to cut (\$, negative)**

The specific negative threshold (e.g., -200.0). If the EA is in a "hostile state" and the sequence is currently floating better than or equal to this loss (e.g., -150.0), it will execute the Safe Close. If the loss is too deep (e.g., -500.0), it will not close, avoiding cutting at the worst possible bottom.

- **Close when out of trading hours**

Considers being outside of the defined Trading Schedule as a "hostile state" for Safe Close evaluation.

- **Close when news filter is active**

Considers an active High-Impact News event as a "hostile state" for Safe Close evaluation.

- **Close when cycle is OFF**

If you manually turn the Cycle OFF, the EA will actively look for an opportunity to Safe Close the remaining trades.

TRADING SCHEDULE (SERVER TIME)

- **Enable trading on Monday (to Sunday)**

Master switches to permit or block trading on specific days of the week.

- **Session 1** *(to Session 4)*

Allows you to define up to 4 specific trading windows per day. Input the time strictly in HH:MM-HH:MM format based on your Broker's Server Time. Leave blank if unused. To trade 24/7, use 00:00-23:59. To trade overnight sessions, use formats like 22:00-03:00.

REMOTE CONTROL

- **Enable remote control via pending orders**

A unique feature allowing you to control the EA remotely from your MT5 mobile app without needing VPS access.

- **Magic price to turn bot ON/OFF**

The specific "Trigger Price". From your phone, place a Buy Limit (or Buy Stop) exactly at this price to turn the EA **ON**. Place a Sell Limit (or Sell Stop) exactly at this price to turn the EA **OFF**. The EA will instantly detect the order, change its state, and delete your pending order.

- **Remote order magic (0 = any)**

Defines which Magic Number the remote orders must have. Leaving it at 0 allows the EA to recognize manual orders placed from your phone.

PANEL SETTINGS

- **Panel X position**

The horizontal coordinate (in pixels) for placing the Neon Dashboard on your chart.

- **Panel Y position**

The vertical coordinate (in pixels) for placing the Neon Dashboard on your chart.