



What has made us strong in the analog world, makes us even stronger in the digital world.

We pioneer motion

BTP platform (admin) user concept

12/2024


We pioneer motion

Role mapping process overview

General information


- *Business user* = user, who is using any application/service from BTP
- *Platform user* = user, who is admin on BTP cockpit or for Cloud admin tools or BTP command line tools
- Direct role to user assignment on BTP only for initial onboarding and POCs
- Services must use BTP / Entra role mapping to avoid manual activities for assigning & revoking authorizations
- Authentication is always via Entra ID

Old status, using S-user



- Access is granted manually, via direct assignment in BTP cockpit.
- S-User is in use (SAP Default)
- Platform user = user with administrative tasks in BTP cockpit
- Business/Application user = user with permission to access BTP applications

Concept for platform users




- Access is granted via BTP Role mapping to Azure AD role
- Schaeffler UserID is in use

Access to Global accounts for platform user

Scope:

Schaeffler managed Global Accounts:

- „CPEA Schaeffler Technologies“
- „Subscriptions Schaeffler Technologies“
- „Cloud ALM“



Available platform user roles on Global Account Level:

- Global Account Administrator for SAP Managed Platform (T1)
- Global Account Viewer (on request)
- Global User and Role Administrator for Authorization Team

Access to Subaccounts for platform user

Subaccount: CF Core IT Services DEV - Role Collections

Name	Description	Roles	User Groups	Actions
Building	Building	Building_Auditor, Building_Admin	RL-BTP-Global-Admin	Copy, Delete, More
CloudConnectorAdministrator	Manages the cloudconnector instance used by other cloud connectors	CloudConnectorAdministrator		Copy, Delete, More
ConnectivityAdministrator	Operates the cloudconnector instance used by other cloud connectors and manages the dedicated configurations, certificates and network trust	ConnectivityAdministrator, 4 More		Copy, Delete, More
DestinationAdministrator	Manages the destination configurations, certificates and subaccount trust	DestinationAdministrator		Copy, Delete, More
Subaccount Administrator	Administrative access to the subaccount	User and Role Administrator, 4 More	RL-BTP-Global-Admin	Copy, Delete, More
Subaccount Viewer	Read-only access to the subaccount	User and Role Auditor, 4 More		Copy, Delete, More
IntegrationAdministrator	Manages the integration instance used by other integrations	IntegrationAdministrator, 4 More		Copy, Delete, More
Full_Admin	Full_Admin	Full_Admin		Copy, Delete, More
Full_Administrator	Full_Administrator	Full_Administrator, Full_Administrator		Copy, Delete, More
Full_Administrator_Admin	Contains Full_Administrator role	Full_Administrator		Copy, Delete, More
Full_Administrator_Auditor	Contains Full_Administrator role	Full_Administrator		Copy, Delete, More
User and Role Administrator	User and Role Administrator	User and Role Administrator		Copy, Delete, More

Available platform user roles on subaccount level:

- Subaccount Administrator for SAP Managed Platform (T1)
- Subaccount Viewer (on request only)
- User and Role Administrator for Authorization Team

Available role mappings for platform user

To avoid manual user assignments to BTP platform user roles, Entra roles are available and mapped to BTP roles.

- Global Account Administrator for SAP Managed Platform (T1)
- Subaccount Administrator for SAP Managed Platform (T1)
 - > *RL-BTP-Global-Admin* (mapped in SAMS to IT-SECURITY_ADMIN=SW)
- Global User and Role Administrator for Authorization Team
- User and Role Administrator for Authorization Team
 - > *RL-BTP-Role-Admin-D (Q/P)* (mapped in SAMS to IAM-AUTH_DEVELOPER=SW)
- Global Account Viewer (on request)
- Subaccount Viewer (on request only)
 - > *RL-BTP-Account-Viewer* (not mapped)

Rolemapping via Entra/SAMS leads to full user lifecycle. No manual effort needed in case of department changes or when employee leaves the company. Roles can be requested via SAMS as for onpremise SAP systems.

Overview

Global Account

Role collection *Global Account Administrator* mapped to *RL-BTP-Global-Admin*

Role collection *Global Account User and Role Administrator* mapped to *RL-BTP-Global-Admin*

Role collection *Global Account Viewer* mapped to *RL-BTP-Account-Viewer*

Subaccounts

- Role collection:

Subaccount Administrator mapped to *RL-BTP-Global-Admin*

support & emergency user dl-sap_cloud_support@schaeffler.com direct assignement, using Default IDP

- Org members:

Right now, no group mapping is possible for Org members, so needed users must be filled in manually. Schaeffler ID is used.

Org Manager = SMP T1 users, in addition support & emergency user dl-sap_cloud_support@schaeffler.com using Default IDP

- Space members:

Right now, no group mapping is possible for Space members, so needed users must be filled in manually. In the past, only S-User was possible, nowadays Schaeffler ID is possible and must be used.

Space manager & Space Developer = SMP T1 users, in addition support & emergency user dl-sap_cloud_support@schaeffler.com using Default IDP

Restrictions / known limitations

- S-User is still needed for Global / Subaccounts managed by SAP or by other companies :
 - SAP Analytics Cloud Global Account
 - SLH_ACRS_SERVICE Global Account
 - Apsolut Global Accounts
 - Vitesco Global Accounts
- Org members must be assigned manually (no AD group mapping possible at the moment, will be delivered in a future upgrade by SAP)
 - This can be requested via ticket to group SAP_MANAGED_PLATFORM_CLOUD _G
- Space members must be assigned manually (no AD group mapping possible at the moment, will be delivered in a future upgrade by SAP)
 - This can be requested via ticket to group SAP_MANAGED_PLATFORM_CLOUD _G