

Role Permissions Overview

When creating roles, permissions are assigned that define what users in that role can see and do. This article explains what each permission does so Admins can configure roles that match user responsibilities and their organization's policies.

🕒 Apr 10, 2026 Knowledge

Article Link URL

[Role Permissions Overview \(https://help.flocksafety.com/s/article/Role-Permissions-Overview\)](https://help.flocksafety.com/s/article/Role-Permissions-Overview)

Question

Answer

When Admins create or edit a role in Flock, they assign Networks and Permissions to ensure users in that role have the appropriate access. Each role clearly identifies the type of access it provides to Flock features.

For instructions on creating, editing, or deleting roles, please view the [How to Manage Roles](https://help.flocksafety.com/s/article/How-to-Manage-Roles) (https://help.flocksafety.com/s/article/How-to-Manage-Roles) article.

Permissions

User must be an Admin with permissions to edit roles and permissions enabled.

Accessing Role Permissions

To access permissions for a role:

- Open the **Roles** sub-tab of the **Admin** page from the green navigation bar
- Click into an existing role or select **'+ Add New Role'** to view the permissions
- On the role configuration page, scroll down to the **Permissions** section to enable or disable feature access for that role. Depending on what Flock package the Admin's organization has, some of these features may be visible or greyed out. If it is greyed out, it means the organization does not have access to those features at this time.

Search Alerts FlockOS Nova VMS Devices Sharing Insights Evidence **Admin**

Admin Profile Organization Devices **Roles** Users Zones Integrations Alerts & FlockOS Billing Contact Directory

< Organization: Flock City PD - Law Enforcement Demo / Roles

Role Name

☐ Admin

Role Category

Networks
0 Networks Enabled [View Networks >](#)

Only the networks enabled will be visible to users assigned to this role.

Permissions

Admin

- ☐ Edit Organization Details
User can access and edit organization details within Admin
- ☐ Manage Billing & Invoices
User can access and edit billing data within Admin
- ☐ Share Networks

Understanding Feature Permissions

Each permission controls access to a specific feature or area in the Flock system. Use the list below to understand what each permission does before enabling it for a role. **'LE Only'** indicates features only available to law enforcement agencies.

Admin

- **Admin:** Allows those assigned to access the Admin page to edit roles, users, Networks, etc.
- **Edit Organization Details:** User can access and edit organization details within Admin
 - Allows those assigned to access the Organization page and edit organization location, enable/disable Lookup, enable Multi-Factor Authentication, etc.
- **Manage Billing & Invoices:** User can access and edit billing data within the Admin Billing tab
- **Share Networks:** User can access the Sharing tab on the main navigation
- **Use File Validator (LE Only):** User can access and run file validation
- **Edit User Profile Settings:** User can edit personal details including name, title, and phone number within User Profile

Search

- **Search:** Users can access and conduct investigative Searches
- **Access Statewide or Nationwide Networks (LE Only):** User can execute a Search or Lookup across statewide or nationwide Networks
- **Visual Search:** User can access Visual Search as an advanced option within Search

- Allows those assigned to take an image and turn it into an investigative lead by using Machine Learning to find similar images
- **Convoy Search:** User can access Convoy Search as an advanced option with Search
 - Allows taking a plate and returning plates that often travel alongside the vehicle of interest
- **Multi-Geo Search:** User can access Multi-Geo Search as an advanced option within Search
 - Allows those assigned to take a list of location/timeframe combinations and return plates that have been seen in all of the locations
- **Freeform Search:** User can use the Freeform Search feature on Networks with feedView permission
 - Allows those assigned to Search for vehicles using plate language descriptions instead of traditional filters

Alerts & FlockOS

- **Custom Hot List Admin (LE Only):** User can access and edit Custom Hot List entries (personal lists and organization lists)
 - Allows those assigned to create, edit, share, delete, and view Custom Hot Lists in their own organizations as well as enable notifications on any Custom Hot List that is shared with their organization
- **Custom Hot List Access (LE Only):** User can access and manage person Custom Hot List entries, but only view organization Custom Hot Lists that they are the selected audience of
- **Manage Suppressed Hits:** User can manage suppressed hits from NCIC Hot List Alerts
 - Allows those assigned to the role to suppress individual plates for their agency
- **Custom Hot List Notes and Attachments (LE Only):** User can include notes and attachments on Custom Hot List entries
- **Audio History Page:** User can access the Audio History Page
- **Real-time Routing (LE Only):** User can activate real-time routing feature within FlockOS
- **Custom Map Layers:** User can view custom map layers within FlockOS
- **CAD Integration (LE Only):** User
 - can access and manage CAD calls within FlockOS
- **FirstTwo Integration (LE Only):** User can view FirstTwo integration results within FlockOS and Alerts
- **Flock911 (LE Only):** User can view Flock911 results within FlockOS and Alerts
- **View FlockOS:** User can view the Map within the FlockOS navigation tab
- **Manage People Detection Alerts:** User can create and edit people detection alerts within Alerts
- **Manage Freeform Alerts:** User can create and edit FreeForm alerts within Alerts

- **Manage Vehicle Description Alerts:** User can create and manage Vehicle Description Alerts within Alerts & FlockOS
 - Allows those assigned to the role to send notifications when vehicles matching a specific set of filter criteria pass a Flock camera; user must have Search and Hot List enabled to utilize this feature
- **View Alert Comments (LE Only):** User can view the comments associated with an Alert within Alerts & FlockOS
- **Write Alert Comments (LE Only):** User can write and manage comments associated with an Alert within Alerts & FlockOS
- **Zone Management:** User can manage zones for the organization
- **View Map Attachments:** User can view attachments within FlockOS
- **Manage Map Attachments:** User can view and edit attachments within FlockOS

VMS

- **VMS Go-Live:** User can view live video feed in the VMS experience
- **VMS Historical:** User can view recorded video feed
- **VMS Download:** User can download recorded video feed
- **VMS PTZ:** User can access and manage live Pan-Tilt-Zoom (PTZ) camera commands
- **VMS PTZ Settings:** User can access and manage PTZ device settings
- **VMS Imaging Settings:** User can access and manage video device imaging settings
- **VMS Camera Views:** User can manage camera views

VMS-Specific Rule

VMS permissions are governed by both the role and Network. For VMS to be enabled on the network:

- The role must have VMS permissions enabled
- The Network must have approved VMS access

If a role has VMS permissions enabled but a user still cannot select VMS for a Network, visit the Network page to confirm that the network is enabled. If the network is enabled and VMS remains unavailable, VMS was not approved for shared access on that Network.

No VMS permissions are available: they are unchecked on the Role page, and/or the organization that shared this network disabled them.

Device Management

- **Devices:** Allows those assigned to the role to access and view the Device Map and Device Networks
- **View Devices:** User can view network map and status pages within Devices
- **Can Configure Intercom Scheduling:** Can configure intercom schedules for eligible devices
- **Device Admin:** Allows those assigned to the role to access the Device Management page to view device status, reboot devices, etc.
- **Device Management:** Allows those assigned to the role to access the 'Device Health Page,' view their devices, status/health of those devices, rename/relocate the devices, and register/unregister devices

Insights

- **Insights:** Allows those assigned to the role to access the Insights Dashboard and sub-tabs
- **View Analytics:** User can access analytics within Insights
- **View Audit Analytics:** User can access all audit-related pages within Insights
- **View Admin Analytics:** User can access additional Admin analytics tab within Insights
- **View Investigation Analytics:** User can access additional Investigation analytics tab within Insights
- **View Traffic Analytics:** User can access additional Traffic analytics tab within Insights
- **View Raven Analytics:** User can access additional R
- **aven analytics** tab within Insights

Planning Portal

- **View Planning Portal:** User can access Planning Portal to get information on the status of their implementation
- **Approve Locations:** User can approve/deny locations in implementation within Planning Portal

Integrations

- **Add Evidence:** User can add search result information as evidence to external evidence management system
 - Allows those assigned to the role to upload images from Flock to Axon's evidence.com (<http://evidence.com/>)

Drones

- **Access Aerodome (LE Only):** User can access Aerodome
- **View Spectator Mode (LE Only):** User can view drone flights within Aerodome

Additional Resources

- [How to Manage Roles](https://help.flocksafety.com/s/article/How-to-Manage-Roles) (https://help.flocksafety.com/s/article/How-to-Manage-Roles)
- [How to Add Users](https://help.flocksafety.com/s/article/How-to-Add-Users-Redesign) (https://help.flocksafety.com/s/article/How-to-Add-Users-Redesign)

Summary ⓘ

When creating roles, permissions are assigned that define what users in that role can see and do. This article explains what each permission does so Admins can configure roles that match user responsibilities and their organization's policies.

Article Created Date

10/7/2024, 4:14 PM

Visible In Internal App

Created By

[Jessi Roman](#), 4/10/2026, 1:38 PM

Visible In Public Knowledge Base

Last Modified By

[Grace Sinclair](#), 4/10/2026, 1:49 PM

Visible to Customer

Last Published Date

4/10/2026, 1:49 PM

Visible to Partner

Article Currency

USD - U.S. Dollar

Was this article helpful?



0



0

Table of Contents

[Permissions](#)

[Accessing Role Permissions](#)

> [Understanding Feature Permissions](#)

[Additional Resources](#)

Related Articles

How to Request Network Sharing on the Map (/s/article/How-to-Request-Network-Sharing-on-the-Map)	 2.6K
How to Accept/Reject Network Sharing Requests - Law Enforcement Agencies Only (/s/article/How-to-Accept-or-Reject-Network-Sharing-Requests)	 1.49K
Receiving Access to Outside Networks (/s/article/Receiving-Access-to-Outside-Networks)	 4.29K
Sharing Access to Your Networks (/s/article/Sharing-Access-to-Your-Networks)	 1.64K
How to Manage Roles (/s/article/How-to-Manage-Roles)	 8.58K
How to Audit Network Sharing (/s/article/How-to-Audit-Network-Sharing)	 1.54K
Authorized Access List (/s/article/Authorized-Access-List)	 2.06K
Law Enforcement Training Webinars (/s/article/Law-Enforcement-Webinar-Trainings)	 9.36K
Getting Started with Flock (/s/article/Getting-Started-with-Flock)	 7.03K
Sharing Your Footage (Non-Law Enforcement) (/s/article/Sharing-Requesting-Footage)	 1.25K

2024 Flock Safety. All right reserved.