

Plugin for RPG Maker MZ

Break Damage Plugin Ver.1.1.3

This plugin adds a shield value to actors and enemies, and when the shield reaches 0, the target enters a Break Stun state.

Main Features

Applies a dedicated damage formula when a specific element is used.

Plays an animation when Break Stun occurs.

“Plays an animation when Break Damage is dealt.

Shield point regeneration rate.

The Break Damage formula can be configured in the same way as the standard damage formula. (This effect can be disabled by turning ON the plugin parameter “Elemental Percentage Damage Immunity”).)

Terms of Use

Credit: Optional

Commercial Use: Allowed

Adult Content: Allowed

Modifications: Allowed

Redistribution: Not allowed, even with modifications

Support is not available for unofficial distribution or modified versions.

When dealing damage to a weak point, break damage is increased by the weak point multiplier. When dealing resistance damage, break damage is reduced by the resistance multiplier.

Specification Change

specifications for the base maximum shield value have been changed.

Base max shield value

Old: Max shield value.

New: Max shield value (no modifiers)

Addition

Max shield value

Max shield value (with modifiers)

How to Configure

Plugin Parameters

- Break stun
Specifies the state to apply when the shield points reach 0. This state can also be applied directly if needed.
- Apply weakness break damage
Executes Break Damage only when the target receives weakness damage.
- Elemental Percentage Damage Immunity
Negates the damage multiplier applied to Break damage when an element is resisted or weak.
- Enable actor break damage
Enables break damage to actors.
- Enable enemy break damage
Enables break damage to enemies. When disabled, break is only enabled for enemies that have <OnBreakDamage> in their note field.
- Break damage animation
Specifies the animation ID to play when Break Damage is triggered.
- Break stun animation
Specifies the animation ID to play when the target enters the Break Stun state.



- Base max shield value
Sets the base maximum shield value.
- Max shield value
Sets the maximum shield value including any increases or decreases.
If the maximum value is 200, and the modified value is 250, it will be capped at 200.”
- Break count variable
Specifies the variable that stores the number of times enemies have been broken.

- Break damage settings

Configures the detailed settings for Break Damage.

1 Method name

Specifies an optional name. Leaving it blank is also fine.

2 Break damage evaluation formula

Specifies the JavaScript formula used to calculate Break Damage.

3 Variance

Sets the variance rate for Break Damage.

4 Element assignment

Specifies the elements for which the elemental Break Damage formula is applied.

Attributes not specified will use the standard Break Damage evaluation formula.

The screenshot shows a dialog box titled 'パラメータ' (Parameters) with a close button (X). It has two tabs: '構造' (Structure) and 'テキスト' (Text). The '構造' tab is active, showing a table for 'ブレイクダメージ設定 (BreakDamageSettings):'. The table has two columns: '名前' (Name) and '値' (Value). The rows are: '名称' (Name), 'ブレイクダメージ評価式' (Break Damage Evaluation Formula) with value '10', '分散度' (Dispersion) with value '0', '属性指定' (Attribute Designation) with value '["7","8"]', and '属性ブレイクダメー...' (Attribute Break Damage) with value '9999'. Below the table is a text area with the message 'ブレイクダメージの設定を行います。' (Please set the Break Damage). At the bottom are 'OK' and 'キャンセル' (Cancel) buttons.

名前	値
名称	
ブレイクダメージ評価式	10
分散度	0
属性指定	["7","8"]
属性ブレイクダメー...	9999

In the above settings, break damage dealt by attacks with Element IDs 7 and 8 will be 9999.

Tag Settings

Break damage

Skill and Item Notetags

<BreakDamageFormula:[formula]> Sets the break damage.

[formula]: Break damage formula(JavaScript)

<BreakAttack:[id]> Sets the Break Damage to apply.

Specify the ID configured in the “Break damage settings” within the plugin parameters.

[id]: Break damage setting id.

Write either of the above tags in the note field of the item or skill.

Break recovery

Skill and Item Notetags

<BreakRecoveryFormula:[formula]> When an action is performed, it restores the target’s shield points.

<BreakRecovery:[id]> When an action is performed, it restores the target’s shield points.

Specifies the ID configured in the Break Damage settings.

Write either of the above tags in the note field of the item or skill.

Actor and Enemy Notetags

<MaxBaseShieldPoint:[value]> “Specifies the maximum shield value without any modifiers. If unspecified, the maximum value of the "Base max shield value" is applied.

[value]:Max value

<MaxShieldPoint:[value]> Specifies the maximum shield value including all modifiers.

If unspecified, the maximum value of the "Max shield value" is applied.

[value]:Max value

Enemy Notetags

<OnBreakDamage> Enables Break Damage only under specific conditions when enemy Break Damage is otherwise disabled.

Trait Notetags

<ShieldRegener:[rate]> Specifies the regeneration rate of shield points.。

[rate]: ±Regen Rate (Ex-Parameter)

<BreakDamageRate:[rate]> Specifies the break-damage rate (percentage).

[rate]: *Damage Rate (Sp-Parameter)

<IncDecMaxShieldPoint:[value]> Specifies the amount by which the maximum shield points are increased or decreased.

[value]: ±Adjustment value (Integer)

Lower limit: 1, Upper limit: Maximum Shield Value (including modifiers)

Parameters available in the evaluation formula

a.nshp or b.nshp: Shield Points

a.nsrg or b.nsrg: Shield Regeneration Rate

item: Skills and Items Used When Attacking

a:Subject

b:Target

v: Game Variable

damage: HP Damage Dealt During Break Attacks.

Settings

I want to apply the Break Gauge only to specific enemies.

Turn off the plugin parameter Enable enemy break damage.

Then add <OnBreakDamage> to the enemy's note field.

Only enemies with <OnBreakDamage> in their notes will have Break Damage enabled.

I want Break Damage to trigger only when the enemy is hit with a weakness.

When the plugin parameter "Apply weakness break damage" is set to ON, Break Damage will only be applied when the attack hits a weakness.

When it is set to OFF, Break Damage will be applied whenever the skill or item deals damage.

Break Damage Mechanics

Break Damage Value $\times$ Attribute Rate (1.0 if disabled)

Log

9/6/2026 Ver.1.1.3

Added a feature to specify a variable that stores the number of times enemies have been broken.

Fixed an issue where Weakness Break Damage was not applied when Ignore Resistance/Weakness Rate Damage was enabled.

Fixed an issue where the Shield Regeneration Rate was not applied correctly.

7/11/2026 Ver.1.1.2

Fixed an issue where maximum shield points were not correctly applied when increasing or decreasing under certain conditions.

7/4/2026 Ver.1.1.1

Fixed an issue where an infinite loop occurred when canceling Break stun.

Fixed an issue where the gauge overflowed when a battle started while exceeding "Base max shield value".

6/27/2026 Ver.1.1.0

Added a function that restores shield points.

Added a feature that allows setting Break Damage Received Rate in Traits.

Added a feature that allows setting the base maximum shield value.

Added a feature that increases or decreases the maximum shield points.

6/20/2026 Ver.1.0.4

Fixed an issue where canceling Break Stance while not in Break Stance would cause the shield gauge to recover.

6/10/2026 Ver.1.0.3

Added processing triggered by "NUUN_ResultActor" updates

6/8/2026 Ver.1.0.2

Fix an issue where the break animation plays again upon defeating an enemy.

5/30/2026 Ver.1.0.1

Fix the spelling errors in the description of the tag that defines the Break Damage formula.

5/26/2026 Ver.1.0.0

First edition.

Plugin for RPG Maker MZ

Break Shield Gauge Plugin Ver.1.0.6

Adds a shield gauge to the actor or enemy.

Main Features

Can be displayed only when selected or when changing values.

Allows specifying the gauge style.

Allows setting a gauge image.

Terms of Use

Credit: Optional

Commercial Use: Allowed

Adult Content: Allowed

Modifications: Allowed

Redistribution: Not allowed, even with modifications

Support is not available for unofficial distribution or modified versions.


How to Configure

Plugin Parameters


- Shield Gauge Style

Specifies the style of the shield gauge.

Default



Diagonal



Step40



Step50



Step60



Image

Displays an image.

Configure gauge images in the actor or enemy gauge image settings.

- Actor gauge display height, enemy gauge display height
Specifies the vertical height of the gauge.
- Background gauge image
Specifies the gauge image displayed at the very back.
- Gauge image
Specifies the gauge image. Please edit the image so that it has no margins.
- Front gauge image
Specifies the gauge image displayed at the front.
- Shield gauge position
Specifies the position where the enemy's shield gauge is displayed.
If 'Above Enemy Image' is selected, the gauge will be displayed above the enemy's graphic.
If 'Below Enemy Image' is selected, the gauge will be displayed below the enemy's graphic.
- Shield gauge display timing
Specifies when the shield gauge is displayed.
If 'Always Display' is selected, the gauge will always be shown.
If 'On Selection' is selected, the gauge will be displayed only when the target is selected.
If 'On Change' is selected, the gauge will be displayed only when the shield points increase or decrease.
If 'On Selection or Change' is selected, the gauge will be displayed only when the conditions for selection or change are met.
- Display frames on change
Specifies the number of frames the gauge is displayed when 'On Change' is selected.

Display in the “NUUN_BattleStyleEX” plugin.

Please select Shield Gauge “NUUN_BreakShieldGaug” from the status options to display.

The only configurable settings are X display col position, Y display row position, X coordinate (relative), and Y coordinate (relative).

The gauge color and gauge width are configured in this plugin's plugin parameters.

Tag Settings

Enemy Character Notes

<ShieldGaugeX:[x]> Specifies the Shield Gauge X of the target enemy.

[X]:Coordinates (Relative)

<ShieldGaugeY:[Y]> Specifies the Shield Gauge Y of the target enemy.

[Y]:Coordinates (Relative)

Log

6/17/2026 Ver.1.0.6

Fixed an issue where the boss gauge was not hidden in NUUN_BreakShieldBossGauge.

6/15/2026 Ver.1.0.5

Fixed an issue where the gauge would remain after a member change.

6/7/2026 Ver.1.0.4

NRP_Afterimage との競合対応。

6/6/2026 Ver.1.0.3

Fixed an issue where the enemy's shield gauge would appear even when the setting to hide it was enabled.

6/3/2026 Ver.1.0.2

Fixed an issue where an error occurred at the start of battle when the shield gauge style was set to Image.

5/30/2026 Ver.1.0.1

Compatibility handling with "AnimatedSVEnemies".

Added a feature to adjust the Shield Gauge's X and Y coordinates for each enemy.

5/26/2026 Ver.1.0.0

First edition.

Plugin for RPG Maker MZ

NUUN_BreakShieldBossGaug Plugin Ver.1.0.0

This plugin displays a shield gauge for bosses during battle.

If multiple bosses are present, multiple gauges will be displayed.

When a boss is defeated, its gauge will disappear.



It is also possible to display them in a single horizontal row.



Can be used together with the “Boss HP Gauge” plugin (NUUN_BossHPGauge). The shield gauge will appear in white.

The images below show example settings.



If ‘Enable Enemy Break Damage’ is set to OFF, enemies without the <OnBreakDamage> tag will not display a shield gauge.

How to Configure

Set this enemy to be recognized as a boss


If the boss has a disappearing effect as a characteristic.

Or add the following tag to the enemy's note field.

Enemy Note Field

<BossEnemy>

Show an HP gauge for boss enemies




Plugin Parameters

- Gauge position

Specify the position of the gauge.


Left



Center



Right



- Vertical gauge display

Specify the vertical display method of the gauge.


Downward

If multiple exist, they will be displayed downward.



Upward

If multiple exist, they will be displayed upward.



- Gauge display column

Specify the number of gauge display columns.

With three bosses in two rows, the display will look as follows.



- Shield gauge Y-coordinate


Specify the Y coordinate of the entire shield gauge.

- Gauge margin

Specify the horizontal padding of the gauge.

margin 0

margin 64




- Gauge vertical spacing

Specifies the vertical display spacing of the gauges.


- Enemy name position

Specify the position of the enemy name.


Left



Center



None




- Name width

Specify the display width of the enemy name.

- Gauge style

Specifies the style of the gauge.


Default



Image


When using the image gauge setting, please select an image.

Diagonal



- Shield gauge color 1

Specifies the shield gauge color (left side).



- Shield gauge color 2

Specifies the shield gauge color (right side).

- Gauge width

Specify the gauge width.

- Gauge height

Specify the gauge height. This setting is disabled in image mode.

- Background gauge image

Specifies the background gauge image. Please set the gauge style to an “Image”.

- Gauge image

Specifies the gauge image.

- Front gauge image

Specifies the front gauge image.

Terms of Use

Credit: Optional

Commercial Use: Allowed

Adult Content: Allowed

Modifications: Allowed

Redistribution: Not allowed, even with modifications

Support is not available for unofficial distribution or modified versions.

Log

6/17/2026 Ver.1.0.0

First edition.