

Plugin for RPG Maker MZ

Boss HP Gauge Plugin Ver.1.0.3

This plugin displays a boss gauge during battles.

If multiple bosses are present, multiple gauges will be displayed.

When a boss is defeated, its gauge will disappear.



It is also possible to display them in a single horizontal row.



How to Configure

Set this enemy to be recognized as a boss


If the boss has a disappearing effect as a characteristic.

Or add the following tag to the enemy's note field.

Enemy Note Field

<BossEnemy>

Show an HP gauge for boss enemies




Plugin Parameters

- Gauge position

Specify the position of the gauge.

Left



Center



Right



- Vertical gauge display

Specify the vertical display method of the gauge.

Downward

If multiple exist, they will be displayed downward.



Upward

If multiple exist, they will be displayed upward.



- Gauge display column

Specify the number of gauge display columns.

With three bosses in two rows, the display will look as follows.




- Boss gauge Y-coordinate

Specify the Y coordinate of the entire boss gauge.


- Gauge margin

Specify the horizontal padding of the gauge.

Margin 0 (Enemy image display ON) Margin 0 (Enemy image display OFF)



Margin 64




- Gauge vertical spacing

Specifies the vertical display spacing of the gauges.


- Enemy name position

Specify the position of the enemy name.


Left



Center



None




- Name width

Specify the display width of the enemy name.

- Gauge style

Specifies the style of the gauge.


Default



Image

When using the image gauge setting, please select an image.

Diagonal



- Gauge Y-offset (relative)
Specify the relative Y-coordinate of the gauge.
- Gauge width
Specify the gauge width.
- Gauge height
Specify the gauge height. This setting is disabled in image mode.
- HP value display
Display the HP value.

Show



Hide



- Background gauge image
Specifies the background gauge image. Please set the gauge style to an “Image”.
- Gauge image
Specifies the gauge image.
- Front gauge image
Specifies the front gauge image.
- Enemy image display
Display the enemy image.

Show




Hide



- Enemy display width
Specify the width of the enemy image to be displayed.
If the image size exceeds the display width, it will be automatically resized.

- Background color

Specify the background color. You can enter color codes in the Text tab.



- Frame color

Specify the frame color.

Terms of Use

Credit: Optional

Commercial Use: Allowed

Adult Content: Allowed

Modifications: Allowed

Redistribution: Allowed

Support will not be provided if the product is downloaded from a source other than the official sales site or if it has been modified.

Log

6/17/2026 Ver.1.0.3

Fixed an issue where, when "Enemy image display" was set to OFF, the gauge margin could not be set to a value smaller than the enemy image width.

6/16/2026 Ver.1.0.2

Added a feature to specify the vertical display spacing of gauges.

6/15/2026 Ver.1.0.1

Fixed so that the vanish effect also recognizes bosses as boss enemies.

6/15/2026 Ver.1.0.0

First edition.