

Plugin for RPG Maker MZ

Break Damage Plugin Ver.1.0.1

This plugin adds a shield value to actors and enemies, and when the shield reaches 0, the target enters a Break Stun state.

Main Features

Applies a dedicated damage formula when a specific element is used.

Plays an animation when Break Stun occurs.

“Plays an animation when Break Damage is dealt.

Shield point regeneration rate.

The Break Damage formula can be configured in the same way as the standard damage formula. (This effect can be disabled by turning ON the plugin parameter “Elemental Percentage Damage Immunity”).)

Terms of Use

Credit: Optional

Commercial Use: Allowed

Adult Content: Allowed

Modifications: Allowed

Redistribution: Not allowed, even with modifications

Support is not available for unofficial distribution or modified versions.

When dealing damage to a weak point, break damage is increased by the weak point multiplier. When dealing resistance damage, break damage is reduced by the resistance multiplier.

How to Configure

Plugin Parameters

- Break stun

Specifies the state to apply when the shield points reach 0. This state can also be applied directly if needed.
- Apply weakness break damage

Executes Break Damage only when the target receives weakness damage.
- Break damage animation

Specifies the animation ID to play when Break Damage is triggered.
- Break stun animation

Specifies the animation ID to play when the target enters the Break Stun state.
- Break damage settings

Configures the detailed settings for Break Damage.

 - 1 Method name

Specifies an optional name. Leaving it blank is also fine.
 - 2 Break damage evaluation formula

Specifies the JavaScript formula used to calculate Break Damage.
 - 3 Variance

Sets the variance rate for Break Damage.
 - 4 Element assignment

Specifies the elements for which the elemental Break Damage formula is applied. Attributes not specified will use the standard Break Damage evaluation formula.

Tag Settings

Skill and Item Notetags

<BreakDamageFormula:[formula]> Sets the break damage.

[formula]: Break damage formula(JavaScript)

<BreakAttack:[id]> Sets the Break Damage to apply.

Specify the ID configured in the “Break damage settings” within the plugin parameters.

[id]: Break damage setting id.

Write either of the above tags in the note field of the item or skill.

Actor and Enemy Notetags

<MaxShieldPoint:[value]> Specifies the maximum shield points.

If left unspecified, the highest value of the base maximum shield points will be used.

[value]: Maximum Value

Enemy Notetags

<OnBreakDamage> Enables Break Damage only under specific conditions when enemy Break Damage is otherwise disabled.

Trait Notetags

<ShieldRegener:[rate]> Specifies the regeneration rate of shield points.。

[rate]: $\pm$ Regen Rate (Ex-Parameter)

Parameters available in the evaluation formula

a.nshp or b.nshp: Shield Points

a.nsrg or b.nsrg: Shield Regeneration Rate

item: Skills and Items Used When Attacking

a:Subject

b:Target

v: Game Variable

Settings

I want to apply the Break Gauge only to specific enemies.

Turn off the plugin parameter Enable enemy break damage.

Then add <OnBreakDamage> to the enemy's note field.

Only enemies with <OnBreakDamage> in their notes will have Break Damage enabled.

I want Break Damage to trigger only when the enemy is hit with a weakness.

When the plugin parameter "Apply weakness break damage" is set to ON, Break Damage will only be applied when the attack hits a weakness.

When it is set to OFF, Break Damage will be applied whenever the skill or item deals damage.

Break Damage Mechanics

Break Damage Value $\times$ Attribute Rate (1.0 if disabled)

Log

5/30/2026 Ver.1.0.1

Fix the spelling errors in the description of the tag that defines the Break Damage formula.

5/26/2026 Ver.1.0.0

First edition.

Plugin for RPG Maker MZ

Break Shield Gauge Plugin Ver.1.0.3

Adds a shield gauge to the actor or enemy.

Main Features

Can be displayed only when selected or when changing values.

Allows specifying the gauge style.

Allows setting a gauge image.

Terms of Use

Credit: Optional

Commercial Use: Allowed

Adult Content: Allowed

Modifications: Allowed

Redistribution: Not allowed, even with modifications


Support is not available for unofficial distribution or modified versions.

How to Configure


Plugin Parameters

- Shield Gauge Style
Specifies the style of the shield gauge.

Default



Diagonal



Step40



Step50



Step60



Image

Displays an image.

Configure gauge images in the actor or enemy gauge image settings.

- Actor gauge display height, enemy gauge display height
Specifies the vertical height of the gauge.
- Background gauge image
Specifies the gauge image displayed at the very back.
- Gauge image
Specifies the gauge image. Please edit the image so that it has no margins.
- Front gauge image
Specifies the gauge image displayed at the front.
- Shield gauge position
Specifies the position where the enemy's shield gauge is displayed.
If 'Above Enemy Image' is selected, the gauge will be displayed above the enemy's graphic.
If 'Below Enemy Image' is selected, the gauge will be displayed below the enemy's graphic.
- Shield gauge display timing
Specifies when the shield gauge is displayed.
If 'Always Display' is selected, the gauge will always be shown.
If 'On Selection' is selected, the gauge will be displayed only when the target is selected.
If 'On Change' is selected, the gauge will be displayed only when the shield points increase or decrease.
If 'On Selection or Change' is selected, the gauge will be displayed only when the conditions for selection or change are met.
- Display frames on change
Specifies the number of frames the gauge is displayed when 'On Change' is selected.

Display in the “NUUN_BattleStyleEX” plugin.

Please select Shield Gauge “NUUN_BreakShieldGaug” from the status options to display.

The only configurable settings are X display col position, Y display row position, X coordinate (relative), and Y coordinate (relative).

The gauge color and gauge width are configured in this plugin’s plugin parameters.

Tag Settings

Enemy Character Notes

<ShieldGaugeX:[x]> Specifies the Shield Gauge X of the target enemy.

[X]:Coordinates (Relative)

<ShieldGaugeY:[Y]> Specifies the Shield Gauge Y of the target enemy.

[Y]:Coordinates (Relative)

Log

6/6/2026 Ver.1.0.3

Fixed an issue where the enemy’s shield gauge would appear even when the setting to hide it was enabled.

6/3/2026 Ver.1.0.2

Fixed an issue where an error occurred at the start of battle when the shield gauge style was set to Image.

5/30/2026 Ver.1.0.1

Compatibility handling with "AnimatedSVEnemies".

Added a feature to adjust the Shield Gauge’s X and Y coordinates for each enemy.

5/26/2026 Ver.1.0.0

First edition.