Search the site **Q**

Java Examples for android.os.BatteryManager

The following java examples will help you to understand the usage of android.os.BatteryManager. These source code samples are taken from different open source projects.

Example 1

```
Project: Rx-receivers-master File: RxBatteryManager.java
                                                                         View Source Code
@Override
public BatteryState call(Intent intent) {
  int health = intent.getIntExtra(BatteryManager.EXTRA_HEALTH, -1);
  int iconSmall = intent.getIntExtra( BatteryManager.EXTRA_ICON_SMALL, -1);
  int level = intent.getIntExtra( BatteryManager.EXTRA_LEVEL, -1);
  int plugged = intent.getIntExtra(BatteryManager.EXTRA PLUGGED, -1);
  boolean present = intent.getBooleanExtra(BatteryManager.EXTRA PRESENT, false);
  int scale = intent.getIntExtra( BatteryManager.EXTRA_SCALE, -1);
  int status = intent.getIntExtra( BatteryManager.EXTRA_STATUS, -1);
  String technology = intent.getStringExtra( BatteryManager.EXTRA_TECHNOLOGY);
  int temperature = intent.getIntExtra(BatteryManager.EXTRA_TEMPERATURE, -1);
  int voltage = intent.getIntExtra( BatteryManager.EXTRA_VOLTAGE, -1);
  return BatteryState.create(BatteryHealth.of(health), iconSmall, level, plugged, present,
scale, BatteryStatus.of(status), technology, temperature, voltage);
```

Example 2

```
Project: Bookdash-android-app-master File: BatteryStatusHelper.java View Source Code

public int getBatteryPercentage() {
    IntentFilter ifilter = new IntentFilter(Intent.ACTION_BATTERY_CHANGED);
    Intent batteryStatus = context.registerReceiver(null, ifilter);
    int level = batteryStatus.getIntExtra( BatteryManager.EXTRA_LEVEL, -1);
    int scale = batteryStatus.getIntExtra( BatteryManager.EXTRA_SCALE, -1);
    float batteryPct = level / (float) scale;
    return Math.round(batteryPct * 100);
}
```

Example 3

```
Project: Bookd_Android_App-master File: BatteryStatusHelper.java View Source Code

public int getBatteryPercentage() {
    IntentFilter ifilter = new IntentFilter(Intent.ACTION_BATTERY_CHANGED);
    Intent batteryStatus = context.registerReceiver(null, ifilter);
    int level = batteryStatus.getIntExtra( BatteryManager.EXTRA_LEVEL, -1);
    int scale = batteryStatus.getIntExtra( BatteryManager.EXTRA_SCALE, -1);
    float batteryPct = level / (float) scale;
    return Math.round(batteryPct * 100);
```

1 2 3 POPULAR **RECENT** java.util.List java.util.ArrayList java.util.LinkedList java.io.IOException java.io.BufferedReader java.io.FileOutputStream java.util.Map java.util.HashMap java.io.InputStreamReader java.io.File java.util.Arrays java.io.InputStream java.io.OutputStream java.util.Set java.util.Collections java.util.lterator



2017年08月23日 09:07

HOME	JAVA	JSTL	STRUTS	SPRING	HIBERNATE	WEBSERVICE	ECLIPSE	API	GUEST POST	
AsJava.comGoogle App EngineVosao			Javatips.net provides unique and complete articles about java and other related						Your email Address	Subscribe
			techr	nologies						

- Privacy Policy
- Contact
- Advertise

Copyright © 2011-2017 Javatips.net, all rights reserved.