


WEEK 4



The image shows the configuration window for PC0 in Cisco Packet Tracer. The window has tabs for 'Physical', 'Config', 'Desktop', 'Programming', and 'Attributes', with 'Config' selected. The 'IP Configuration' section is expanded, showing the 'FastEthernet0' interface. The 'IP Configuration' section has two radio buttons: 'DHCP' (unselected) and 'Static' (selected). The 'Static' configuration fields are filled with the following values:

Field	Value
IPv4 Address	192.168.1.2
Subnet Mask	255.255.255.0
Default Gateway	192.168.1.1
DNS Server	0.0.0.0

The 'IPv6 Configuration' section also has two radio buttons: 'Automatic' (unselected) and 'Static' (selected). The 'Static' configuration fields are filled with the following values:

Field	Value
IPv6 Address	
Link Local Address	FE80::202:17FF:FE18:9538
Default Gateway	
DNS Server	

The '802.1X' section is expanded, showing the 'Use 802.1X Security' checkbox (unchecked). The 'Authentication' dropdown is set to 'MD5'. The 'Username' and 'Password' fields are empty.

PC1

Physical Config **Desktop** Programming Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address: 192.168.2.2

Subnet Mask: 255.255.255.0

Default Gateway: 192.168.2.1

DNS Server: 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address: /

Link Local Address: FE80::20A:41FF:FE60:415

Default Gateway:

DNS Server:

802.1X

☐ Use 802.1X Security

Authentication: MD5

Username:

Password:

☐ Top

Router0

Physical Config **CLI** Attributes

IOS Command Line Interface

```

2 FastEthernet interface(s)
1 Low-speed serial(sync/async) network interface(s)
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface s0/3/0
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#no shutdown
%LINK-5-CHANGED: Interface Serial0/3/0, changed state to down
Router(config-if)#no shutdown
Router(config-if)#interface Fa0/0
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#wr
Building configuration...
[OK]
Router#

```

☐ Top

Copy Paste

Router1

Physical Config CLI Attributes

IOS Command Line Interface

Press RETURN to get started!

```
Router>enable
Translating "enable"...domain server (255.255.255.255)
% Unknown command or computer name, or unable to find computer address

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface s0/0/0
Router(config-if)#ip address 10.0.0.2 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial10/0/0, changed state to up

Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial10/0/0, changed state to up

Router(config-if)#interface fa0/0
Router(config-if)#ip address 192.168.2.1 255.255.255.0
Router(config-if)#no shutdown

% Invalid input detected at '^' marker.

Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr
Building configuration...
[OK]
Router#
```

Copy Paste

Top



PC0

Physical Config Desktop Programming Attributes

Command Prompt

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 192.168.2.2

Pinging 192.168.2.2 with 32 bytes of data:

Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.
Reply from 192.168.1.1: Destination host unreachable.

Ping statistics for 192.168.2.2:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>|
```

☐ Top

Router0

Physical Config CLI Attributes

IOS Command Line Interface

```
Router con0 is now available

Press RETURN to get started.

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)# eigrp 1

% Invalid input detected at '^' marker.

Router(config)#router eigrp 1
Router(config-router)#network 10.0.0.0 0.255.255.255
Router(config-router)#network 192.168.1.0 0.0.0.255
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr
Building configuration...
[OK]
Router#
```

☐ Top

Copy Paste

