



WEEK 5



PC1

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address

Subnet Mask

Default Gateway 0.0.0.0

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address 2001:3::2 / 64

Link Local Address FE80::20D:B0FF:FEED:A802

Default Gateway 2001:3::1

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

Router0

Physical Config CLI Attributes

IOS Command Line Interface

If you require further assistance please contact us by sending email to export@cisco.com.

Cisco CISC02911/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor Board ID FTX152400K3
3 Gigabit Ethernet interfaces
2 Low-speed serial(sync/asynch) network interface(s)
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249956K bytes of ATA System CompactFlash 0 (Read/Write)

--- System Configuration Dialog ---



Would you like to enter the initial configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ipv6 uni
Router(config)#ipv6 unicast-routing
Router(config)#interface g0/0
Router(config-if)#ipv6 address 2001:1::1/64
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
Router(config-if)#interface s0/0/0
Router(config-if)#ipv6 address 2001:2::1/64
Router(config-if)#no shutdown
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Router(config-if)#exit
Router(config)#

Copy Paste

Top



Router0

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ipv6 router eigrp 1
Router(config-rtt)#eigrp router-id 2.2.2.2
Router(config-rtt)#exit
Router(config)#interface g0/0
Router(config-if)#ipv6 eigrp 1
Router(config-if)#interface s0/0/0
Router(config-if)#ipv6 eigrp 1
Router(config-if)#exit
Router(config)#exit
Router#
$SYS-S-CONFIG_1: Configured from console by console

Router#wr
Building configuration...
[OK]
Router#show ipv6 interface b
GigabitEthernet0/0 [up/up]
FE80::206:2AFF:FEBD:2C01
2001:1::1
GigabitEthernet0/1 [administratively down/down]
unassigned
GigabitEthernet0/2 [administratively down/down]
unassigned
Serial0/0/0 [up/up]
FE80::206:2AFF:FEBD:2C01
2001:2::1
Serial0/0/1 [administratively down/down]
unassigned
Vlan1 [administratively down/down]
unassigned
Router#
```

Copy Paste

☐ Top

Router1

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#show ipv6 interface b
GigabitEthernet0/0 [up/up]
FE80::260:3EFF:FE6D:E301
2001:3::1
GigabitEthernet0/1 [administratively down/down]
unassigned
GigabitEthernet0/2 [administratively down/down]
unassigned
Serial0/0/0 [up/up]
FE80::260:3EFF:FE6D:E301
2001:2::2
Serial0/0/1 [administratively down/down]
unassigned
Vlan1 [administratively down/down]
unassigned
Router#show ipv6 route
IPv6 Routing Table - S entries
Codes: C - Connected, L - Local, S - Static, R - RIP, B - BGP
U - Per-user Static route, M - MIPv6
I1 - ISIS L1, I2 - ISIS L2, IA - ISIS interarea, IS - ISIS summary
ND - ND Default, NDp - ND Prefix, DCE - Destination, NDr - Redirect
O - OSPF intra, OI - OSPF inter, ON1 - OSPF ext 1, ON2 - OSPF ext 2
ON1 - OSPF NSSA ext 1, ON2 - OSPF NSSA ext 2
D - EIGRP, EX - EIGRP external
C 2001:2::/64 [0/0]
via Serial0/0/0, directly connected
L 2001:2::2/128 [0/0]
via Serial0/0/0, receive
C 2001:3::/64 [0/0]
via GigabitEthernet0/0, directly connected
L 2001:3::1/128 [0/0]
via GigabitEthernet0/0, receive
L FF00::/8 [0/0]
via Null0, receive
Router#
```

Copy Paste

☐ Top

Router1

Physical Config CLI Attributes

IOS Command Line Interface

```
FE80::260:3EFF:FE6D:E301
2001:2::2
Serial0/0/1      [administratively down/down]
unassigned
Vlan1            [administratively down/down]
unassigned
Router#show ipv6 route
IPv6 Routing Table - 5 entries
Codes: C - Connected, L - Local, S - Static, R - RIP, B - BGP
       U - Per-user Static route, M - MIPv6
       I1 - ISIS L1, I2 - ISIS L2, IA - ISIS interarea, IS - ISIS summary
       ND - ND Default, NDp - ND Prefix, DCE - Destination, NDr - Redirect
       O - OSPF intra, OI - OSPF inter, OE1 - OSPF ext 1, OE2 - OSPF ext 2
       ON1 - OSPF NSSA ext 1, ON2 - OSPF NSSA ext 2
       D - EIGRP, EX - EIGRP external
C 2001:2::/64 [0/0]
   via Serial0/0/0, directly connected
L 2001:2::2/128 [0/0]
   via Serial0/0/0, receive
C 2001:3::/64 [0/0]
   via GigabitEthernet0/0, directly connected
L 2001:3::1/128 [0/0]
   via GigabitEthernet0/0, receive
L FF00::/8 [0/0]
   via Null0, receive
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ipv6 router eigrp 1
Router(config-rtr)#no shutdown
Router(config-rtr)#no hutdown
^
% Invalid input detected at '^' marker.

Router(config-rtr)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr
Building configuration...
[OK]
Router#
```

Copy Paste

Top

Router0

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ipv6 router eigrp 1
Router(config-rtr)#eigrp router-id 2.2.2.2
Router(config-rtr)#exit
Router(config)#interface g0/0
Router(config-if)#ipv6 eigrp 1
Router(config-if)#interface s0/0/0
Router(config-if)#ipv6 eigrp 1
Router(config-if)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr
Building configuration...
[OK]
Router#show ipv6 interface b
GigabitEthernet0/0      [up/up]
FE80::206:2AFF:FEBD:2C01
2001::1
GigabitEthernet0/1      [administratively down/down]
unassigned
GigabitEthernet0/2      [administratively down/down]
unassigned
Serial0/0/0             [up/up]
FE80::206:2AFF:FEBD:2C01
2001:2::1
Serial0/0/1             [administratively down/down]
unassigned
Vlan1                   [administratively down/down]
unassigned
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ipv6 router eigrp 1
Router(config-rtr)#no shutdown
Router(config-rtr)#
%DUAL-5-NBRCHANGE: IPv6-EIGRP 1: Neighbor FE80::260:3EFF:FE6D:E301 (Serial0/0/0) is up: new
adjacency
Router(config-rtr)#
```

Copy Paste

Top

05:05:30

ulation

ire Las

7:03 PM 9/17/2025

