

10.4 Lab: Resolve Print Services Support Tickets

null

Candidate: omar santiago (osantiago162@gmail.com)**Time Spent:** 05:58**Score:** 100%

Task Summary

Required Actions

- ✓ Add the HP Photosmart printer to the Workspace
- ✓ Connect the printer to the computer
- ✓ Provide power to the printer
- ✓ Set the HP Photosmart Plus printer as the default printer
- ✓ Close the first ticket
- ✓ Add a dot matrix printer to the IT Office
- ✓ Close the second ticket

Explanation

Complete this lab as follows:

1. From ITAdmin, determine the needs and possible fixes for Gerry's help desk ticket.
 - a. From the taskbar, search for and select **Issue Trax**.
 - b. Maximize the window for better viewing.
 - c. Select ticket **#20** and determine the best course of action.
 - d. Leave the ticket maximized so you can see the details.
2. Identify the appropriate printer based on the scenario and move it to the Workspace.
 - a. From the upper left, select **Floor 1 Overview**.
 - b. Under *Lobby*, select **Hardware**.
 - c. Under Inventory, expand **Peripherals**.
 - d. Identify the printer that best meets the scenario's requirements.
 - e. Drag the **HP Photosmart Plus** printer to the Workspace.
3. Connect the printer to the computer.
 - a. Switch to the back view of the laptop.
 - b. Switch to the back view of the printer and examine the connection ports.
 - c. In the Inventory, click **Peripherals** to go back to the main menu, then expand **Cables**.

- d. Select **USB Cable (A/B)**.
- e. From the Selected Item pane:
 - Drag the **USB Type B Connector** to the port on the back of the printer.
 - Drag the **USB Type A Connector** to a USB port on the back of the laptop.
4. Provide power to the printer.
 - a. Under Inventory, select **Power Adapter for HP**.
 - b. From the Selected Item pane:
 - Drag the **Power Adapter, DC connector** to the port on the back of the printer.
 - Drag the **Power Adapter, AC connector** to an AC power port on the wall outlet.
5. Verify the installation and set the printer as the default printer.
 - a. Switch to the front view of the laptop.
 - b. Select the monitor to access the operating system.
 - c. Right-click **Start** and then select **Settings**.
 - d. Select **Bluetooth & devices**.
 - e. From the right pane, select **Printers & scanners**.
Your newly installed printer is shown.
 - f. Select **HP Photosmart Plus**.
 - g. Select **Set as default**.
6. Add a comment to the ticket and close the ticket.
 - a. From the upper left, select **Floor 1 Overview**.
 - b. Under IT Administration, select **ITAdmin**.
 - c. In the *New Comment* field for the open ticket, add a comment to indicate that the printer has been installed.
 - d. Select the + (plus sign) to add the comment.
 - e. From the top-right of the ticket, select **Closed**.
 - f. Select the **left arrow** to view the remaining ticket.
7. Resolve the next ticket
 - a. Select ticket #21.
 - b. From the upper left, select **IT Administration**.
 - c. In the Peripherals section of the Inventory, drag the **Okidata** dot-matrix printer to the Workspace.
 - d. Select the monitor to go back to the operating system
 - e. Type a comment in the comment field to indicate the job is done, then press the **plus sign**.
 - f. At the top right, set the ticket to **Closed**.

Copyright © 2026 CompTIA, Inc. All rights reserved.