NAME

ovn−detrace − convert ‘‘ovs−appctl ofproto/trace’’ output to combine OVN logical flow information.

SYNOPSIS

ovn−detrace < *file*

Common options:

[**−h** | **−−help**] [**−V** | **−−version**]

DESCRIPTION

The **ovn−detrace** program reads **ovs−appctl ofproto/trace** output on stdin, looking for flow cookies, and expand each cookie with corresponding OVN logical flows. It expands logical flow further with the north-bound information e.g. the ACL that generated the logical flow, when relevant.

OPTIONS

−h

−−help Prints a brief help message to the console.

−V

−−version

Prints version information to the console.

−−ovnsb=*server*

The OVN Southbound DB remote to contact. If the **OVN_SB_DB** environment variable is set, its value is used as the default. Otherwise, the default is **unix:@RUNDIR@/ovnsb_db.sock**, but this default is unlikely to be useful outside of single-machine OVN test environments.

−−ovnnb=*server*

The OVN Northbound DB remote to contact. If the **OVN_NB_DB** environment variable is set, its value is used as the default. Otherwise, the default is **unix:@RUNDIR@/ovnnb_db.sock**, but this default is unlikely to be useful outside of single-machine OVN test environments.

−−ovs= Also decode flow information (like OVS ofport) from the flows by connecting to the OVS DB.

−−no-leader-only

Connect to any cluster member, not just the leader. The option works for OVN Southbound DB and OVN Northbound DB.

−−ovsdb=*server*

The OVS DB remote to contact if **−−ovs** is present. If the **OVS_RUNDIR** environment variable is set, its value is used as the default. Otherwise, the default is **unix:@RUNDIR@/db.sock**, but this default is unlikely to be useful outside of single-machine OVN test environments.

−p *privkey.pem*

−−private−key=*privkey.pem*

Specifies a PEM file containing the private key used as **ovn−detrace**’s identity for outgoing SSL connections.

−c *cert.pem*

−−certificate=*cert.pem*

Specifies a PEM file containing a certificate that certifies the private key specified on **−p** or **−−private−key** to be trustworthy. The certificate must be signed by the certificate authority (CA) that the peer in SSL connections will use to verify it.

−C *cacert.pem*

−−ca−cert=*cacert.pem*

Specifies a PEM file containing the CA certificate that **ovn−detrace** should use to verify certificates presented to it by SSL peers. (This may be the same certificate that SSL peers use to verify the certificate specified on **−c** or **−−certificate**, or it may be a different one, depending on the PKI design in use.)

SEE ALSO

ovs−appctl(8),**ovn−sbctl**(8),**ovn−nbctl**(8),**ovn−trace**(8)