

SESSION - 19

User Administration and Security



Table of Contents

Table of Contents **1**

Users and Groups in AEM ***2***

Introduction **2**

Objectives **2**

Users **2**

Groups **2**

Built-in Users and Groups **2**

Permissions in AEM **3**

Permissions and ACLs **3**

Actions **3**

Permissions **4**

Impersonating another User **4**

Managing Users and Groups ***4***

Exercise 1: Creating Users and Groups 5

Exercise 2: Self completing exercise 7

Users and Groups in AEM

Introduction

This session we will describe how to configure and maintain user authorization and also describes the theory behind how authentication and authorization work in AEM.

Objectives

After completing this module, you will be able to:

- Create Users in AEM
- Create Groups in AEM
- Assign Groups to User
- Assign Users to Group
- Add permissions to User and Groups

Users

Users will log in to AEM with their account. Each user account is unique and holds the basic account details, together with the privileges assigned.

Users are often members of Groups, which simplify the allocation of these permissions and/or privileges.

Groups

Groups are collections of users and/or other groups; these are all called Members of a group.

Their primary purpose is to simplify the maintenance process by reducing the number of entities to be updated, as a change made to a group is applied to all members of the group. Groups often reflect:


- a role within the application; such as someone who is allowed to surf the content, or someone who is allowed to contribute content.
- your own organization; you may want to extend the roles to differentiate between contributors from different departments when they are restricted to different branches in the content tree.

Therefore groups tend to remain stable, whereas users come and go more frequently.

With planning and a clean structure, the use of groups can reflect your structure, giving you a clear overview and an efficient mechanism for updates.

Built-in Users and Groups

AEM WCM installs a number of users and groups. These can be seen when you first access the Security Console after installation as shown:



To see the complete details of the users and their description follow the official documentations here.

https://docs.adobe.com/content/help/en/experience-manager-65/administering/security/security.html

Permissions in AEM

AEM uses ACLs to determine what actions a user or group and can take and where it can perform those actions.

Permissions and ACLs


Permissions define who is allowed to perform which actions on a resource. The permissions are the result of access control evaluations.

You can change the permissions granted/denied to a given user by selecting or clearing the checkboxes for the individual AEM actions . A check mark indicates that an action is allowed. No checkmark indicates that an action is denied.

Where the checkmark is located in the grid also indicates what permissions users have in what locations within AEM (that is, which paths).


Actions

Actions can be performed on a page (resource). For each page in the hierarchy, you can specify which action the user is allowed to take on that page. Permissions enable you to allow or deny an action.



Permissions

Permissions give users and groups access to AEM functionality on AEM pages.
You browse permissions by path by expanding/collapsing the nodes and you can track the permission inheritance up to the root node.
You allow or deny permissions by selecting or clearing the appropriate check boxes.



Impersonating another User

With the Impersonate functionality a user can work on behalf of another user.
This means that a user account can specify other accounts that can operate with their account. In other words, if user-B is allowed to impersonate user-A, then user-B can take actions using the full account details of user-A.
This allows the impersonator accounts to complete tasks as if they were using the account they are impersonating; for example, during an absence or to share an excessive load short-term.

Managing Users and Groups


Users include people using the system and foreign systems making requests to the system.

A **group** is a set of users.

Both can be configured using the User Administration functionality within the Security Console.

You access all users, groups, and associated permissions using the Security console. All the procedures described in this section are performed in this window which is Admin console and can be accessed via this link:


Navigate directly to **https://<server>:<port>/useradmin** . Be sure you log into AEM as an administrator. The following window displays:




Exercise 1: Creating Users and Groups

To create a new user or group:


1. In the Security console tree list, click Edit and then either Create User or Create Group .



2. Enter the required details, according to whether you are creating a user or a group.
3. If you select **Create User**, you enter the Login ID, first and last name, e-mail address and a password. By default, AEM creates a path based on the first letter of the last name, but you can select another path.



4. If you select **Create Group**, you enter a group ID and an optional description.



5. Click Create . The user or group you created appears in the tree list.

Exercise 2: Self completing exercise

Create three users **author**, **editor** and **legal** and assign them workflow administration group. We will use these users for the next sessions. Follow this documentation for this exercise.
https://docs.adobe.com/content/help/en/experience-manager-65/administering/security/security.html

NOTE : There will be few questions from this particular topic in certification so read multiple times this product documentation.