

Get started with Cloud Data Sense for Amazon FSx for ONTAP

Cloud Manager

Julia August 31, 2021

Table of Contents

Get started with Cloud Data Sense for Amazon FSx for ONTAP				
	Before you begin			
	Quick start			
	Discovering the data sources that you want to scan			
	Deploying the Cloud Data Sense instance.			
	Enabling Cloud Data Sense in your working environments			
	Verifying that Cloud Data Sense has access to volumes			
	Enabling and disabling compliance scans on volumes			

Get started with Cloud Data Sense for Amazon FSx for ONTAP

Complete a few steps to get started with Cloud Data Sense for FSx for ONTAP.

Before you begin

- You need an active Connector in AWS to deploy and manage Data Sense.
- The security group you selected when creating the working environment must allow traffic from the Cloud Data Sense instance. You can find the associated security group using the ENI connected to the FSx for ONTAP file system and edit it using the AWS Management Console.

AWS security groups for Linux instances

AWS security groups for Windows instances

AWS elastic network interfaces (ENI)



At this time, you can scan NFS volumes only.

Quick start

Get started quickly by following these steps or scroll down for full details.



Discover the data sources that contain the data you want to scan

Before you can scan FSx for ONTAP volumes, you must have an FSx working environment with volumes configured.



Deploy the Cloud Data Sense instance

Deploy Cloud Data Sense in Cloud Manager if there isn't already an instance deployed.



Enable Cloud Data Sense and select the volumes to scan

Click **Data Sense**, select the **Configuration** tab, and activate compliance scans for volumes in specific working environments.



Ensure access to volumes

Now that Cloud Data Sense is enabled, ensure that it can access all volumes.

The Cloud Data Sense instance needs a network connection to each FSx for ONTAP subnet.

- Make sure NFS ports 111 and 2049 are open to the Data Sense instance.
- NFS volume export policies must allow access from the Data Sense instance.



Manage the volumes you want to scan

Select or deselect the volumes you want to scan and Cloud Data Sense will start or stop scanning them.

Discovering the data sources that you want to scan

If the data sources you want to scan are not already in your Cloud Manager environment, you can add them to the canvas at this time.

For FSx for ONTAP, Cloud Manager must be set up to discover the configuration.

Deploying the Cloud Data Sense instance


Deploy Cloud Data Sense if there isn't already an instance deployed.

Data Sense should be deployed in the same AWS network as the Connector for AWS and the FSx volumes you wish to scan.

Enabling Cloud Data Sense in your working environments

You can enable Cloud Data Sense for FSx for ONTAP volumes.

1. At the top of Cloud Manager, click **Data Sense** and then select the **Configuration** tab.



2. To scan all volumes in a working environment, click **Activate Scanning for All Volumes**.

When enabled in this manner, full "mapping and classification" scanning is performed on all volumes.

If you want to enable scanning only for certain volumes, or if you only want to perform "mapping-only" scanning, click **or select Volumes** and then choose the volumes you want to scan.

See Enabling and disabling compliance scans on volumes for details.

Result

Cloud Data Sense starts scanning the volumes you selected in the working environment. Results will be available in the Compliance dashboard as soon as Cloud Data Sense finishes the initial scans. The time that it takes depends on the amount of data—it could be a few minutes or hours.

Verifying that Cloud Data Sense has access to volumes

Make sure Cloud Data Sense can access volumes by checking your networking, security groups, and export policies.

Steps

1. On the Configuration page, click View Details to review the status and correct any errors.

For example, the following image shows a volume Cloud Data Sense can't scan due to network connectivity issues between the Data Sense instance and the volume.



Make sure there's a network connection between the Cloud Data Sense instance and each network that includes volumes for FSx for ONTAP.




For FSx for ONTAP, Cloud Data Sense can scan volumes only in the same region as Cloud Manager.

- 3. Ensure NFS ports 111 and 2049 are open to the Data Sense instance.
- 4. Ensure NFS volume export policies include the IP address of the Data Sense instance so it can access the data on each volume.

Enabling and disabling compliance scans on volumes

You can stop or start mapping scans, or mapping and classification scans, in a working environment at any time from the Configuration page. We recommend that you scan all volumes.



То:	Do this:
Enable mapping-only scans on a volume	Click Map
Enable full scanning on a volume	Click Map & Classify

То:	Do this:
Enable full scanning on all volumes	Move the Map & Classify All slider to the right
Disable scanning on a volume	Click Off
Disable scanning on all volumes	Move the Map & Classify All slider to the left



New volumes added to the working environment are automatically scanned only when the **Activate Compliance for all Volumes** setting is enabled. When this setting is disabled, you'll need to activate scanning on each new volume you create in the working environment.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.