FlyUX

App wireframes v 1.0
Sarab Sundin 2022



If you are logged in, your name is below "Welcome", and the "Login" button is not available on the "home" screen.

The "Book" button is clearly marked with color. Tapping it will select the "Book" tab.



The selected tab is highlighted in color.

A new page opens when you tap on "From", "To", "When" or "Travellers".
The user then comes back to this screen.

The last few searches are displayed in a list for quick selection when selecting this tab.

Selections are filled in as they are being made, like in the first row.

The button is disabled by default and only becomes enabled if all values are filled in.

The "From" and "To" screens are the same. Only the title differs.



The selected tab is highlighted in color.

When you tap on the search field, the area below becomes empty.
When you start typing, you get suggestions

Nearby airports are visible by default.

Tapping a row selects the airport and returns to "Search".

When you select the "Favourites" tab, the cities you have selected as favourites are listed below.

When you tap on a star, it becomes colored and the airport is added to favourites.
To remove it from favourites, tap the star again. The star then becomes transparent.



Returns to "Search" without saving selection.

Days that have passed are brighter and not tappable.

Months are presented as you scroll up or down.

"Done" becomes tappable when you have selected the necessary date(s). Tapping it returns to "Search" with selected date(s).

When "One way" is selected, only one date is selectable.

A start and an end date is selected one after the other to create a range.

The selected date range is marked in color.

If a date range is already selected and a new date is tapped, the range is cleared and the selected date becomes the new start date.

Returns to "Search" without saving selection.



"Done" is enabled as long as there is at least 1 traveller selected. Tapping it returns to "Search" with selection.

There is a pre-selected value of 1 adult



Arrows are tappable for moving to previous and next day.

The first row is by default expanded to display that you have several class options. This does not happen for inbound flight selection.

Tapping "Compare" opens a new page, to compare the different price classes. Then back to this page.

Tap the arrow to expand the row to reveal more travel options. Tap the arrow again to collapse the row.
The row is expanded until collapsed. Several rows can be expanded at the same time.

The selection is marked with color when you tap on it. If you tap the same again, it is deselected. If you tap another option, the previous selection is deselected and the new selection is selected instead.

Continue becomes tappable once a travel option has been selected.



This screen functions like "Outbound", only that the first line is not expanded by default.

Continue becomes tappable once a travel option has been selected.



Opens up a new page with more information about the flight. Then back to this page.

"Login" appears in the summary if you are not logged in.



If there is only one traveller, this page is not part of the flow, you go directly to fill in traveller information.

A new page opens when you tap on the row. Once you have filled in the information about the passenger, you go back to this page. Then "Enter details" is replaced by the passenger's name.

Continue becomes tappable once details for all travellers are filled in.



Returns to "Travellers" without saving details.

If there is already details for the selected traveller, it will be pre-filled.

"Done" becomes tappable when all fields are filled in. Tapping it will go back to "Travellers" with saved details.

Keyboard rolls up.

Man, woman options roll up.

Keyboard for date rolls up.

Keyboard adapted for email rolls up.

Number keyboard rolls up.



A new page opens when you tap on "Select seat", "Your bags", Meals onboard", "Lounge access".

If a selection has been made, it will appear here.
-No selected seats / Seats selected.
-No check-in luggage / Check-in luggage selected
-No meals / Meals selected
-No selection / Lounge access

Opens up a new page with T&C.

The button is enabled when you have checked in the "terms & conditions" box.

Returns to "Extras" without saving selection.

The selected tab is highlighted in color.

Name and chair number are stated if you have chosen a chair. If you have not chosen a chair, it says "No chosen seat".



"Done" is always tappable.

You can switch between "Outbound" and "Inbound" and then tap on "Done" when / if you have selected seats. You do not have to select seats to move on.

The seat is marked with color when you tap on it. If you tap on the seat again, the selection is deselected.
You choose seats in the order of the names in the list above.
The first tap selects the seat for the first traveller, etc. If there are two names in the list and you tap a third time, a new seat is selected for the first person in the list.

Scrolling here will reveal the rest of the plane.



Keyboard rolls up.

Numeric keyboard scrolls up.

Month/year selection rolls up.

The button will be enabled when all information is filled in.