

1. Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

Connecting and Testing a USB Webcam

Steps Performed

1. Connected the USB webcam to an available USB port on the computer.
2. Waited for Windows to detect the device automatically.
3. Installed the required drivers (if prompted) or allowed Windows to install them automatically.
4. Opened **Device Manager** and verified that the webcam appeared under **Cameras**.
5. Opened the default **Camera** app in Windows.
6. Confirmed that the webcam displayed live video correctly.
7. Captured a photo using the Camera app to verify that the webcam was functioning properly.

2. Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

Setting Up a Local Printer and Printing a Test Page

Steps Performed

1. Connected the printer to the computer using a USB cable (or connected it to the local network for a network printer).
2. Turned on the printer and ensured it was ready for use.
3. Allowed Windows to detect the printer automatically.
4. Installed the correct printer driver from the manufacturer's CD or downloaded it from the manufacturer's website.
5. Opened **Settings > Devices > Printers & Scanners** and verified that the printer appeared in the list.
6. Selected the printer and clicked **Manage**.
7. Chose **Print a Test Page** to check whether the printer was functioning properly.

Result

The printer was successfully installed, the correct driver was configured, and a test page was printed successfully, confirming that the installation was completed correctly.

3. Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem.

Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.

Simulating and Resolving a 'Printer Not Detected' Issue Using Device Manager

Step 1: Simulate the Problem

- Unplug the printer's USB cable from the computer.
- Verify that the printer is no longer available in **Settings > Devices > Printers & Scanners**.

Step 2: Open Device Manager

- Right-click the **Start** button and select **Device Manager**.

Step 3: Check for Error Indicators

- Expand the **Printers** section.
- Look for the printer or any device with a **yellow warning icon (!)**, which indicates a hardware or driver issue.

Step 4: Reconnect the Printer

- Plug the USB cable back into the computer.
- Wait a few seconds for Windows to detect the printer.

Step 5: Scan for Hardware Changes

- In Device Manager, click **Action > Scan for hardware changes**.
- Windows will search for newly connected devices and reinstall the printer if necessary.

Step 6: Verify the Solution

- Ensure that the printer appears in Device Manager without any warning icons.
- Open **Settings > Devices > Printers & Scanners** and confirm that the printer is listed.
- Print a test page to verify that the printer is working properly.

4. A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications.

Hint: Check if another app is using the webcam or if Zoom permissions are enabled.

Troubleshooting Webcam Video Not Displaying in Zoom

Step 1: Verify the Webcam

- Open the default Camera app.
- Confirm that the webcam is working correctly.

Step 2: Close Other Applications

- Exit the Camera app and any other applications that might be using the webcam, such as Microsoft Teams or Skype.
- A webcam can usually be used by only one application at a time.

Step 3: Check Zoom Camera Settings

- Open Zoom.
- Go to Settings > Video.
- Select the correct webcam from the Camera drop-down menu.
- Verify that a video preview is displayed.

Step 4: Check Windows Camera Permissions

- Open Settings > Privacy > Camera.
- Ensure Camera access for this device is turned on.
- Enable Allow apps to access your camera.
- Enable Allow desktop apps to access your camera, which includes Zoom.

Step 5: Restart Zoom and the Computer

- Close Zoom completely and reopen it.
- If the problem persists, restart the computer and try again.

Step 6: Update Zoom and Webcam Drivers

- Install the latest version of Zoom.
- Open Device Manager, locate the webcam under Cameras, and update the driver if necessary.