

o\_que\_samba

# O que é protocolo samba

## 1. Referências

1. [Instalando e Configurando o Servidor Samba no Linux Debian - versão 24/06/2020](#)

## Arquivo de configuração

Sample configuration file for the Samba suite for Debian GNU/Linux.

This is the main Samba configuration file. You should read the smb.conf(5) manual page in order to understand the options listed here. Samba has a huge number of configurable options most of which are not shown in this example

Some options that are often worth tuning have been included as commented-out examples in this file.

- When such options are commented with ">>", the proposed setting differs from the default Samba behaviour
- When commented with ">", the proposed setting is the default behaviour of Samba but the option is considered important enough to be mentioned here

NOTE: Whenever you modify this file you should run the command "testparm" to check that you have not made any basic syntactic errors.

===== Global Settings =====

[global]

Browsing/Identification >>>

Change this to the workgroup/NT-domain name your Samba server will part of  
workgroup = itms

Networking >>>>

The specific set of interfaces / networks to bind to This can be either the interface name or an IP address/netmask>> interface names are normally preferred

interfaces = 127.0.0.0/8 eth0

Only bind to the named interfaces and/or networks>> you must use the 'interfaces' option above to use this. It is recommended that you enable this feature if your Samba machine is not protected by a firewall or is a firewall itself. However, this option cannot handle dynamic or non-broadcast interfaces correctly.

bind interfaces only = yes

 Debugging/Accounting >>>>

This tells Samba to use a separate log file for each machine that connects log file = /var/log/samba/log.%m

Cap the size of the individual log files (in KiB). max log size = 1000

We want Samba to only log to /var/log/samba/log.{smbd,nmbd}. Append syslog@1 if you want important messages to be sent to syslog too. logging = file

Do something sensible when Samba crashes: mail the admin a backtrace panic action = /usr/share/samba/panic-action %d

 Authentication >>>>>>>

Server role. Defines in which mode Samba will operate. Possible values are "standalone server", "member server", "classic primary domain controller", "classic backup domain controller", "active directory domain controller".

Most people will want "standalone server" or "member server". Running as "active directory domain controller" will require first running "samba-tool domain provision" to wipe databases and create a new domain. server role = standalone server

obey pam restrictions = yes

This boolean parameter controls whether Samba attempts to sync the Unix password with the SMB password when the encrypted SMB password in the passdb is changed. unix password sync = yes

For Unix password sync to work on a Debian GNU/Linux system, the following parameters must be set (thanks to Ian Kahan <[kahan@informatik.tu-muenchen.de](mailto:kahan@informatik.tu-muenchen.de) for sending the correct chat script for the passwd program in Debian Sarge). passwd program = /usr/bin/passwd %u passwd chat = *Enter\snew\s\spassword:\* %n\n Retype\snew\s\spassword:\* %n\n password\supdated\ssuccessfully* .

This boolean controls whether PAM will be used for password changes when requested by an SMB client instead of the program listed in 'passwd program'. The default is 'no'. pam password change = yes

This option controls how unsuccessful authentication attempts are mapped to anonymous connections map to guest = bad user

 Domains >>>>>>>>>>

The following settings only takes effect if 'server role = classic primary domain controller', 'server role = classic backup domain controller' or 'domain logons' is set

It specifies the location of the user's profile directory from the client point of view) The following required a [profiles] share to be setup on the samba server (see below)



Allow users who've been granted usershare privileges to create public shares, not just authenticated ones  
usershare allow guests = yes

===== Share Definitions =====

[homes] comment = Home Directories browseable = no

By default, the home directories are exported read-only. Change the next parameter to 'no' if you want to be able to write to them.  
read only = yes

File creation mask is set to 0700 for security reasons. If you want to create files with group=rw permissions, set next parameter to 0775.  
create mask = 0700

Directory creation mask is set to 0700 for security reasons. If you want to create dirs. with group=rw permissions, set next parameter to 0775.  
directory mask = 0700

By default, \server\username shares can be connected to by anyone with access to the samba server. The following parameter makes sure that only "username" can connect to \server\username This might need tweaking when using external authentication schemes  
valid users = %S

Un-comment the following and create the netlogon directory for Domain Logons (you need to configure Samba to act as a domain controller too.)

[netlogon] comment = Network Logon Service  
path = /home/samba/netlogon  
guest ok = yes read only = yes

Un-comment the following and create the profiles directory to store users profiles (see the "logon path" option above) (you need to configure Samba to act as a domain controller too.) The path below should be writable by all users so that their profile directory may be created the first time they log on

[profiles] comment = Users profiles  
path = /home/samba/profiles  
guest ok = no  
browseable = no create mask = 0600  
directory mask = 0700

[printers] comment = All Printers  
browseable = no path = /var/tmp  
printable = yes guest ok = no  
read only = yes create mask = 0700

Windows clients look for this share name as a source of downloadable printer drivers  
[print\$] comment = Printer Drivers  
path = /var/lib/samba/printers  
browseable = yes  
read only = yes guest ok = no  
Uncomment to allow remote administration of Windows print drivers. You may need to replace 'lpadmin' with the name of the group your admin users are members of. Please note that you also need to set appropriate Unix permissions to the drivers directory for these users to have write rights in it

write list = root, @lpadmin