



VISOR User Guide

Virtual Intelligence Simulator Overlay & Radar

Version 0.9.8.2 Beta | CephasMedia LLC | info@cephasmedia.com

What is VISOR?

VISOR (Virtual Intelligence Simulator Overlay & Radar) is a real-time telemetry overlay for iRacing that includes only essential information such as position, fuel remaining, relative gaps, and a radar.

Important: VISOR only works when iRacing is running in **borderless windowed mode**.

Getting Started

1. Launch VISOR - Three windows will appear:
 - **Main Window:** Race information overlay
 - **Radar Window:** Proximity and spotter information
 - **Configuration Window:** Settings and customization
2. Position the Main Window and Radar Window where you want them on screen
3. Configure which information to display using the Configuration Window
4. Click "Done" in the Configuration Window to save positions and settings
5. Launch iRacing and start a session - VISOR will automatically connect

Configuration Window

The Configuration Window lets you customize VISOR's display layout. Here you can toggle individual elements (Rows 0-5 and the Radar window) on or off based on what information you want visible during your race.

Window Size Presets

Choose from three size options that scale both the Main Window and Radar Window:

- **Small (60% scale):** Minimal screen space, smaller text
- **Medium (80% scale):** Balanced visibility and space
- **Large (100% scale):** Maximum readability (default)

Drag and Position

When the Configuration Window is open, both Main and Radar Windows display drag handles in the top-left corner. Click and drag to reposition. Positions save when you click "Done."

Main Window Display Elements

Row 0: Gear Indicator & Class Position

Gear Indicator: Displays current gear ("R" for reverse, "N" for neutral, numbers for forward gears) using a digital-style font for quick readability.

Class Position: Shows your position within your car class (not overall). In practice/qualifying: based on fastest lap times. In races: real-time track position.

Row 1: Time & Fuel Remaining

Time/Laps Remaining: In timed sessions, shows time remaining (HH:MM:SS or MM:SS). In lap-limited sessions, shows laps remaining for leader (+1 to iRacing's value). In qualifying, shows personal laps completed/total allowed. Displays "Final Lap" on the white flag and "FINISHED" on the checkered flag.

Fuel Remaining: Estimates laps of fuel using a rolling 3-lap average of consumption. Updates after each lap (Format: "X.X Laps"). Most accurate after 3+ consistent laps.

Row 2: Lap Delta Bar

Real-time visual comparison vs. your session best lap. The bar grows from the center: **Right (green):** faster, **Left (red):** slower, **Center:** matching pace. Range is ± 3 seconds.

Row 3: Lap Times

Last Lap: Your most recently completed lap time (M:SS.mmm). **Best Lap:** Your fastest valid lap this session (M:SS.mmm). Both values reset on a new session.

Row 4: Relative Positioning Table

Shows 7 rows: 3 cars ahead, your car (yellow), and 3 behind. Gap times are calculated like a physical transponder loop to measure true time gaps between cars. Automatically hidden in Lone Qualifying sessions.

Visual Indicators: Yellow = you, White = same lap, Blue = lapped by you, Red = lapping you.

Pit Road: Cars on pit road display a "PIT" label and use gray proximity segments.

Stationary Cars: Stopped vehicles on track display their physical distance in feet (capped at 999ft) in bold yellow text.

Proximity Bar: Features a dynamic 5-segment warning system that fills as cars get closer, scaling from an informational 8.0-second gap down to a critical 0.6-second gap. Automatically filters disconnected drivers.

Row 5: Warnings Row

Incident Counter: Session incidents (0x, 4x, etc.) with color progression.

Pace Warning (

Persistent Dot (•): Remains until your lap is within 1% of best pace.

PIT Warning: Flashing yellow when time lost per lap exceeds pit stop cost. (This feature is still in development).

Radar Window

Top-down proximity view with 5 vertical zones (far left, near left, center, near right, far right). Your car: green rectangle in center. Other cars: colored by class. Detection range: ~5 car lengths ahead/behind. Can be toggled on/off in the Configuration window.

Zone Highlighting

Zones highlight based on iRacing spotter: left zone = car left, right zone = car right, both = cars both sides, two zones = multiple cars. Matches native spotter calls.

Visibility

Automatically fades out when no cars in range, fades in when cars approach. Hidden automatically in Lone Qualifying.

Understanding Session Behavior

Practice and Qualifying

Position: Based on fastest lap time. **Relative:** Sorted by proximity. **Updates:** On faster lap completions.

Race Sessions

Position: Real-time track position (lap + distance). **Relative:** Cars physically near you. **Lapped traffic:** Color-coded (blue/red).

Lone Qualifying

Relative Table and Radar Window automatically hide (no other cars on track simultaneously).

Tips for Use

- **First Launch:** Drag windows using handles while Configuration Window is open
- **Testing:** Changes apply in real-time, no restart needed
- **Window Positions:** Saved automatically on "Done"
- **Fuel:** Most accurate after 3+ consistent laps

Contact

For questions, bug reports, or feedback:

Email: info@cephasmedia.com

License: Personal use only. See LICENSE.txt for full terms.