MASKINHALLEN · USER MANUAL · VERSION 2.0

GRUND

KICK · BASS · RUMBLE · SELF-PLAYING BASSLINE

The low end of techno in one machine. Kick, bass and rumble share the bottom and never clash.



VST3 · AU · LV2 · STANDALONE
MACOS · WINDOWS · LINUX

MASKINHALLEN

CONTENTS

01 Welcome
02 Install
03 Unlock with your key
04 Your first minute
05 KICK
06 BASS
07 KLISTER and RUMBLE
08 BASSLINE
09 Presets
10 Troubleshooting

01 WELCOME

GRUND 2 is the low end of techno in one machine: KICK, BASS and RUMBLE that share the bottom and never clash, plus a BASSLINE that plays itself.

Most tracks fall apart in the low end: the kick and the bass fight, the rumble muddies everything. In GRUND they are built to work together. The kick is always tuned to the key, the bass steps aside while the kick sounds, and the rumble pumps with the kick. Pick a style, turn a few knobs, and the floor moves.

- **KICK**: five kick types and five patterns, tuned to the key.
- **BASS**: seven engines, from pure sub to acid.
- **KLISTER** (glue): the bass gets out of the kick's way.
- **RUMBLE**: the kick through a dark room, distorted and filtered.
- **BASSLINE**: seven styles that write the bassline for you.
- **24 presets** in eight categories.

SWEDISH LABELS

`Ton / Längd`	Tune / Length	`Klick / Driv / Nivå`	Click / Drive / Level
`Bas / Oktav / Glid`	Bass / Octave / Glide	`Klister`	Glue (sidechain duck)
`Basgång`	Bassline	`Täthet / Variation`	Density / Variation
`Tonart / Skala`	Key / Scale	`Moll`	Minor

THE WINDOW



02 INSTALL

Unzip the file for your system. You get a folder called **GRUND** (on Mac and Windows: GRUND-macOS and GRUND-Windows). Then run the installer for your system and restart your DAW (or rescan plug-ins). GRUND shows up as an instrument.

MACOS

1. Double-click `GRUND-macOS.zip` in Downloads.
2. Open Terminal and run:
   `bash ~/Downloads/GRUND-macOS/installera.command`
3. Quit your DAW completely and start it again.

VST3, AU and a standalone app. macOS 11 or newer, Intel or Apple Silicon. The installer copies the plug-ins and removes macOS's block on downloaded plug-ins.

WINDOWS

1. Right-click `GRUND-Windows.zip` and choose **Extract all**.
2. Open the `GRUND-Windows` folder and right-click `installera.bat` → **Run as administrator**.
3. If Windows says "Windows protected your PC": **More info** → **Run anyway**.

VST3 (in C:\Program Files\Common Files\VST3) and a standalone .exe. 64-bit Windows 10 or 11.

LINUX

1. Unzip `GRUND-Linux.zip`.
2. Run `bash ~/Downloads/GRUND/installera-linux.sh`. It copies the plug-ins to `~/.vst3` and `~/.lv2`.
3. Rescan plug-ins in your DAW (Bitwig, Reaper, Ardour and others).

VST3 and LV2, 64-bit x86 Linux (built on Ubuntu 22.04).

> SWEDISH OR ENGLISH
> The machines have Swedish names on the panel. One click on `SV | EN` in the header switches labels, menus and tooltips to English. Your choice is remembered for every MASKINHALLEN machine.

---

03 UNLOCK WITH YOUR KEY

Your purchase comes with a licence key: four groups of four characters, like `XXXX-XXXX-XXXX-XXXX`. You find it in the Payhip email and on your receipt.

1. Open GRUND. Until it is unlocked, the window shows **UNLOCK GRUND**.
2. Paste the whole key in the field and press `UNLOCK`.
3. Done. You only need to do this once per computer: every MASKINHALLEN machine on the computer finds the key. A bundle key unlocks every machine.

The key is not case sensitive, and I/L and O/0 are treated as the same character, so a typo there does not matter. If it says the key does not work, check that the whole key was pasted. You can use your key on your own computers.

THE FREE DEMO

Every machine has a free demo with the same sound engine. Some presets and functions are locked, and the demo has its own name (GRUND DEMO), so it can sit next to the full version. Buying the full version is what unlocks everything; install it and paste your key.

UPDATES

Updates are free for life. Download the new zip from your Payhip receipt link and run the installer again. Your projects and your key are kept.

04 YOUR FIRST MINUTE

1. Put GRUND on an instrument track and press play. GRUND follows your tempo; kick and bassline start by themselves.
2. Step through presets with `<` `>` at the top, or open the list.
3. Change the bassline style (RULLANDE, GALOPP, OFFBEAT ...) and press the dice in the BASGÅNG section for a new line in the same style.
4. Turn `KLISTER` up until kick and bass sit like one instrument.
5. Add `RUMBLE` for the dark, pumping low end.

05 KICK

`KICK`	Kick on or off.
`Type`	**PUNCH**, **DJUP** (deep), **HÅRD** (hard), **SÖNDER** (broken, distorted) and **MJUK** (soft).
`Pattern`	**4/4**, **4/4 + SPÖK** (with ghost kicks), **BRUTEN** (broken), **HALV** (half time) and **AV** (off).
`TON`	Tune. The kick always follows the key; TON moves it from there.
`LÄNGD · KLICK · DRIV · NIVÅ`	Length, click, drive and level.

The kick note (C1) also triggers the kick from MIDI.

06 BASS

ENGINE	CHARACTER
`SUB`	Pure, round sub.
`MICRO`	Short bouncing micro-plucks for minimal.
`GUMMI`	Rubber: a springy, rounded bass.
`REESE`	Detuned, moving and wide.
`FM`	Metallic, knocking FM bass.
`DUB`	Deep, soft dub bass.

ENGINE	CHARACTER
SYRA	Acid with resonance and glide.

OKTAV, LÄNGD, TON (tone/brightness), DRIV, GLID (glide) and NIVÅ.

07 KLISTER AND RUMBLE

KLISTER (GLUE)

The bass ducks while the kick sounds. High = kick and bass never collide. The DUCK meter in OUT shows it working. A kick from outside (for example BETONG on the sidechain input) also pushes the bass away.

RUMBLE

The kick sent through a dark room, distorted and filtered, pumping with the kick: the rolling low end of modern techno. RUMBLE sets the amount; LÄNGD, TON and DRIV shape the room's length, colour and grit.

08 BASSLINE

With BASGÅNG on, GRUND writes and plays the bassline itself. The sixteen steps are shown on the right; the step playing now is outlined and the kicks are marked underneath.

STYLE	FEEL
RULLANDE	Rolling 16ths between the kicks.
GALOPP	Galloping.
OFFBEAT	Classic offbeat bass.
MICRO	Sparse micro-house plucks.
DUBB	Slow dub notes with space.
SYRA	Acid lines with slides and accents.
DRÖN	Drone: long held notes.

- Key · Scale: minor, Phrygian, Dorian, pentatonic or fixed (one note).
- TÄTHET (density), VARIATION (a little new every bar, a fill every fourth) and SWING.
- The dice gives a new bassline in the same style. The same settings always give the same line.

MIDI

With the bassline on, the keys you play move the key. With it off, you play the bass yourself. The kick note (C1) hits the kick.

09 PRESETS

24 presets in eight categories: ROLLANDE, HYPNOS, STUDS, DUB, SYRA, INDUSTRI, RUMBLE and DRÖN. The dice in each section randomises only that section; the big dice at the top randomises everything. Projects from GRUND 1 open on the first preset, since the controls are new.

> COMING IN GRUND 2
> LEARN FROM THE KICK, CLUB CHECK, MIDI out and 150+ presets. Free updates.

10 TROUBLESHOOTING

GRUND does not show up	Quit the DAW completely and start it again, or rescan plug-ins. On Mac, run the installer again: it removes macOS's quarantine on the plug-in. On Windows, check that `GRUND.vst3` is in C:\Program Files\Common Files\VST3.
macOS says the plug-in is damaged	That is macOS's block on downloaded files. Run `bash ~/Downloads/GRUND-macOS/installera.command` again.
Windows protected your PC	Click **More info** → **Run anyway**. The plug-ins are not signed with a paid certificate.
The key does not work	Paste the whole key, including the dashes. A key for one machine only unlocks that machine; a bundle key unlocks all.
No sound	Press play in the DAW: the machines follow the transport. Instruments go on an instrument track, effects on an audio track or bus.

Anything else? Ask through the store, and the person who built the machine answers.

MASKINHALLEN