Hide/Show Code Blocks

Operation	Keystroke	Function	Note
HideShow Minor Mode	When working with source code files, you can use the Hide/Show minor mode to collapse and expand blocks of code, where the concept of "block of code" depends on the specific programming language. For example C-like programming language use braces to delimit blocks, while in Lisp languages use parentheses for all blocking. • When a block is hidden (collapsed) it is replaced by "" surrounded by the block delimiter of the specific programming language. • The PEL commands below are all invoked via the <f11> / key prefix and can be used anytime since they activates the Hide/Show mode if it is not already active. This is not so for the standard Emacs commands bound to the C-c @ key prefix: for those you must activate the Hide/Show mode explicitly to activate the key prefix. • Once the Hide/Show minor mode is active the mode-line will show "hs" and the C-c @ key prefix is available. If you want to restore everything in view, turn the mode and remove availability of the C-c @ key prefix turn the mode off. PEL provides the <f11> // key for that (it also activates the mode). • This is not limited to C-like or Lisp-like programming languages. It works with Python and most other programming languages. • You may want to hide comments as well when collapsing code: you can use <f11> ; ~ to toggle visibility of comments, see § Comments table for more info on this.)</f11></f11></f11>		
Toggle Hide/Show Minor Mode	<f11> / /</f11>	(hs-minor-mode &optional ARG)	Toggle Hide/Show minor mode to selectively hide/show code and comment blocks. • With a prefix argument ARG, enable the mode if ARG is positive, and disable it otherwise. • When hideshow minor mode is on: • The menu bar is augmented with hideshow commands and the hideshow commands are enabled. • The line-mode shows 'hs'.
Toggle visibility of all blocks in buffer	<f11> / a</f11>	(pel-toggle-hide-all)	Toggle hide/show of all blocks. • Activates the Hide/Show mode if not already active (and hide all blocks)
Toggle visibility of current block	• <f11> / b • C-c @ C-c • C-c @ C-e</f11>	(pel-toggle-hide-block) (hs-toggle-hiding)	Toggle hide/show of current block.
Hide (collapse) current block	• <f11> / h • C-c @ C-h • C-c @ C-d</f11>	(pel-hide-block &optional END) (hs-hide-block &optional END)	Select a block and hide it. With prefix arg, reposition at END.
Show (expand) current block	• <f11> / s • C-c @ C-s</f11>	(pel-show-block &optional END) (hs-show-block &optional END)	Select a block and show it. • With prefix arg, reposition at END.
Hide (collapse) all blocks in buffer	• <f11> / H • C-c @ C-M-h • C-c @ C-t</f11>	(pel-hide-all) (hs-hide-all)	Hide all top level blocks, displaying only first and last lines.
Show (expand) all blocks in buffer	• <f11> / S • C-c @ C-M-s • C-c @ C-a</f11>	(pel-show-all) (hs-show-all)	Show all blocks.
Hide all blocks 1 level below current block	<f11> / 1</f11>	(pel-hide-level-1)	Hide all blocks 1 level below the current block. Useful in language like Python to show the methods of a class.
Hide all blocks 2 level below current block	<f11> / 2</f11>	(pel-hide-level-2)	Hide all blocks 2 level below the current block.
Hide all blocks 3 level below current block	<f11> / 3</f11>	(pel-hide-level-3)	Hide all blocks 3 level below the current block.
Hide all blocks 4 level below current block	<f11> / 4</f11>	(pel-hide-level-4)	Hide all blocks 4 level below the current block.
Hide all blocks N levels below this block.	C-u n C-c @ C-1	(hs-hide-level ARG)	Hide all blocks ARG levels below this block. Like all other commands that take a numeric argument, the numeric argument (shown in the keystroke column as C-u n, can also be typed with the M-number)

Hide/Show Code Blocks — References

Topic & Link	Description	
GNU Emacs Manual - Hideshow minor mode	Emacs section that describes the Hide/Show minor mode.	