Mode Line Control

Description	<u>Keystroke</u>	Function	Notes / Example description
Emacs Mode Line See: <u>S Customize</u>	An early version of a page that will describe tools to manage the mode line. Currently PEL does not provide much support for controlling Emacs mode line. It provides the following: The pel-pkg-for-modeline customization group that contains the user-options used to activate mode line related packages: The delight external package PEL activates it when the pel-use-delight user-option is turned on (set to t). Access this customization group with <f11> M-d <f2>. When delight is used, PEL activates short lighters for some minor-modes. The following commands can be used to provides the activation of extra information shown on the mode line.</f2></f11>		
Open this PDF file. See also: <u>▼ Help/Info</u>	<f11> M-d <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>Node Line</u> local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
<u>∑ Customize</u> PEL mode line support	<f11> M-d <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL mode line support • If OTHER-WINDOW is non-nil (use C - u), display in another window.
<u>> Customize</u> Emacs mode line	<f11> M-d <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs mode line support: mode-line • If OTHER-WINDOW is non-nil (use C - u), display in another window.
Toggle which-function-mode to display name of current function at point See also: • <u>N Help/Info</u> • <u>N Menus</u>	• <f11> ? f • <f11> M-d f</f11></f11>	(which-function-mode &optional ARG)	Toggle mode line display of current function (Which Function mode). • With a prefix argument ARG, enable Which Function mode if ARG is positive, and disable it otherwise. • The which-function-mode is a global minor mode. When enabled, the current function name is continuously displayed in the mode line, in certain major modes. ⚠ Detection of functions and variables depend on the imenu functionality. If you modify the content of a buffer, you need to force a menu rescan to get proper results. You can force a rescan with pel-imenu-rescan, bound to <f11> <f10> r.</f10></f11>
	Identify the major modes where you want this activated in the which-function-mode user-option with M-x customize-option which-function-mode. • With PEL you can use: • <f11> ? <f3> to access the which-func customization group. Note that it will provide access to the customization group even when the feature has not yet been loaded. • <f11> <f2> o which-function-mode RET to access the user-option directly.</f2></f11></f3></f11>		
Toggle display of <u>ace-window</u> number on window mode line See also: <u>▼ Windows</u>	• <f11> w # • <f11> M-d #</f11></f11>	(ace-window-display-mode &optional ARG)	Toggle the ace-window-display-mode, a minor mode that displays the ace window number of each window inside the left hand side of its mode line. Requires the ace-window external package. PEL activates it when the pel-use-ace-window user-option is turned on. Use < f11 > w <f2> to access the customization group where you can turn it on.</f2>