🚧 Emacs support for Nim 🚧

Description	Keystroke	Function	Note
Nim Editing	Emacs does not provide any built-in mode for nim. 🔳 To activate support for nim on PEL, the **pel-use-nim** user-option must be turned on (set to **t**). • When **pel-use-nim is** turned on the **`<f11> SPC n`** prefix is made available. PEL provides the following user-options to download and activate nim supporting Emacs packages. It uses the tuareg-mode as the major mode for nim files. 📦 The **nim-mode** external package is required. 🔳 PEL installs and activates it when the **pel-use-nim-mode** user-options is turned on. 🚧 PEL support for nim is not complete. More commands should be provided and documented. nim support is preliminary.		
Open this PDF file. See also: ∑ **Help/ Info**	**`<f11> SPC n <f1>`** **`<f12> <f1>`**	**(pel-help-pdf** &optional OPEN-WEB-PAGE)	Open the 𝔓𝔩 **- Nim** local PDF. If the prefix argument (like **C–u** or **M––**) is used, then it opens the remote GitHub hosted raw PDF instead. If the **pel-flip-help-pdf-arg** user-option is set it's the other way around.
∑ Customize PEL nim support	**`<f11> SPC n <f2>`** **`<f12> <f2>`**	**(pel-customize-pel** &optional OTHER-WINDOW)	Customize PEL nim support. • If OTHER-WINDOW is non-nil (use **C–u**), display in another window.
∑ Customize Emacs nim support	**`<f11> SPC n <f3>`** **`<f12> <f3>`**	**(pel-customize-library** &optional OTHER-WINDOW)	Customize Emacs nim support: nim • If OTHER-WINDOW is non-nil (use **C–u**), display in another window.
Comments			
Toggle display of comments in buffer or active region See also: ∑ **Comments**	**`<f11> ; ;`**	**(hide/show-comments-toggle** &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. 📦 This requires the **hide-comnt.el** package (see ∑ **Comments**). 🔳 PEL activates it when the **pel-use-hide-comnt** user option is **t**.

Emacs & Nim — References

Document	Notes