

Lesson 13 Demo 02

Creating Load Balancer

Objective: To create a load balancer for distributing incoming network traffic

Tools required: Azure account with administrator access


Prerequisites: None

Steps to be followed:

1. Create a load balancer

Step 1: Create a load balancer

1.1 In the Azure portal, click on **Create a resource**



1.2 In the **Create a Resource** page, scroll and select **Networking** from the left panel, and click on **Load Balancer**

[Home](#) >

Create a resource

Developer tools

DevOps

Identity

Integration

Internet of Things

IT & Management Tools

Media

Migration

Mixed Reality

Monitoring & Diagnostics

Networking

Security

Storage

Web


[Create](#) | [Docs](#)



Front Door and CDN profiles

[Create](#) | [Docs](#)



Traffic Manager profile

[Create](#) | [Docs](#) | [MS Learn](#)



Network security group

[Create](#) | [Docs](#) | [MS Learn](#)



Virtual network gateway

[Create](#) | [Docs](#) | [MS Learn](#)



Application Gateway

[Create](#) | [Docs](#) | [MS Learn](#)



Load Balancer

[Create](#) | [Docs](#) | [MS Learn](#)

1.3 In the **Create load balancer** page, navigate to the **Basics** tab. For the **Resource group**, select **Create new**, provide a **Name**, and click **OK**.

Home > Create a resource >

Create load balancer

Basics Frontend IP configuration Backend pools Inbound rules Outbound rules Tags Review + create

Azure load balancer is a layer 4 load balancer that distributes incoming traffic among healthy virtual machine instances. Load balancers uses a hash-based distribution algorithm. By default, it uses a 5-tuple (source IP, source port, destination IP, destination port, protocol type) hash to map traffic to available servers. Load balancers can either be internet-facing where it is accessible via public IP addresses, or internal where it is only accessible from a virtual network. Azure load balancers also support Network Address Translation (NAT) to route traffic between public and private IP addresses. [Learn more.](#)

Project details

Subscription *

Resource group *
[Create new](#)

Instance details

Name *

Region *

[Download a template for automation](#) [Give feedback](#)

1.4 Provide the **Instance details** as shown below, and then click on **Next : Frontend IP configuration >**

Instance details

Name *

Region *

SKU * ☒ Standard ☐ Gateway ☐ Basic

Type * ☒ Public ☐ Internal

Tier * ☒ Regional ☐ Global

[Download a template for automation](#) [Give feedback](#)

1.5 Click on + Add a frontend IP configuration

Home > Create a resource >

Create load balancer

Basics **Frontend IP configuration** Backend pools Inbound rules Outbound rules Tags Review + create

A frontend IP configuration is an IP address used for inbound and/or outbound communication as defined within load balancing, inbound NAT, and outbound rules.

+ Add a frontend IP configuration

Name ↑↓	IP address ↑↓	Virtual network ↑↓	Subnet ↑↓
Add a frontend IP to get started			

Review + create < Previous Next : Backend pools > Download a template for automation Give feedback

1.6 Provide the details as shown under Add frontend IP configuration page and click Add

Home > Create a resource >

Create load balancer

Basics **Frontend IP configuration** Backend pools Inbound rules Outbound rules Tags Review + create

A frontend IP configuration is an IP address used for inbound and/or outbound communication as defined within load balancing, inbound NAT, and outbound rules.

+ Add a frontend IP configuration

Name ↑↓	IP address ↑↓
Add a frontend IP to get started	

At least 1 frontend IP needs to be added for creating a Load Balancer

Review + create < Previous Next : Backend pools > Download a template for automation Give feedback

Add frontend IP configuration

Name * FrontIP ✓

IP version ☒ IPv4 ☐ IPv6

IP type ☒ IP address ☐ IP prefix

Public IP address * (New) PublicIP Create new

Gateway Load balancer ☐ None

Add

1.7 Click **Review + create**

[Home](#) > [Create a resource](#) >

Create load balancer ...

[Basics](#)
[Frontend IP configuration](#)
[Backend pools](#)
[Inbound rules](#)
[Outbound rules](#)
[Tags](#)
[Review + create](#)

A frontend IP configuration is an IP address used for inbound and/or outbound communication as defined within load balancing, inbound NAT, and outbound rules.

+ Add a frontend IP configuration

Name ↑↓	IP address ↑↓
FrontIP	PublicIP (To be created)

[Review + create](#)
[< Previous](#)
[Next : Backend pools >](#)
[Download a template for automation](#)
[Give feedback](#)

1.8 After the validation is passed, click on the **Create** button

[Home](#) > [Create a resource](#) >

Create load balancer ...

 Validation passed

Basics


Subscription	Simplilearn HOL 100710
Resource group	(new) RG01
Name	LoadBalancer1
Region	East US
SKU	Standard
Tier	Regional
Type	Public

Frontend IP configuration

Frontend IP configuration name	FrontIP
Frontend IP configuration IP address	To be created

[Create](#)
[< Previous](#)
[Next >](#)
[Download a template for automation](#)
[Give feedback](#)

Wait for your deployment to complete and the following screenshot will appear:



By following these steps, you have successfully created a load balancer to manage incoming traffic.