




PNETLab1 Topology

R1

```
R1#sh ip int brief
Interface              IP-Address      OK? Method Status  Prot
ocol
Ethernet0/0            172.50.0.1      YES TFTP   up      up
Ethernet0/1            1.0.0.1         YES TFTP   up      up
Ethernet0/2            unassigned      YES TFTP   down    down
Ethernet0/3            unassigned      YES TFTP   down    down

R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int e0/1
R1(config-if)#ip helper-add 172.50.0.2
R1(config-if)#exit
R1(config)#exit
R1#
*Aug  3 16:54:02.481: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

R3

```
R3(config)#exit
R3#sh ip
*Aug  3 16:52:17.169: %SYS-5-CONFIG_I: Configured from console by console
R3#sh ip int brief
Interface              IP-Address      OK? Method Status  Prot
ocol
Ethernet0/0            12.0.0.2        YES TFTP   up      up
Ethernet0/1            29.0.0.1        YES TFTP   up      up
Ethernet0/2            unassigned      YES TFTP   down    down
Ethernet0/3            unassigned      YES TFTP   down    down

R3#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#int e0/1
R3(config-if)#ip helper-add 12.0.0.1
R3(config-if)#exi
R3(config)#exit
R3#
*Aug  3 16:53:12.212: %SYS-5-CONFIG_I: Configured from console by console
R3#
```

network CCNA

SALES

MGMT

R2

```
R2#conf t
Translating "conf t"

% Bad IP address or host name
% Unknown command or computer name, or unable to find computer address
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool Mgmt
R2(dhcp-config)#network 129.23.0.0 255.255.0.0
R2(dhcp-config)#default-router 129.23.0.1
R2(dhcp-config)#lease 1 2 3
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded 129.23.0.1 129.23.0.50
R2(config)#exit
R2#
*Aug  3 16:33:52.757: %SYS-5-CONFIG_I: Configured from console by console
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool Production
R2(dhcp-config)#network 212.25.0.0 255.255.255.0
R2(dhcp-config)#default-router 212.25.0.1
R2(dhcp-config)#lease 1 2 3
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 212.25.0.1 212.25.0.50
R2(config)#exit
R2#
*Aug  3 16:35:27.896: %SYS-5-CONFIG_I: Configured from console by console
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool Sales
R2(dhcp-config)#network 1.0.0.0 255.0.0.0
R2(dhcp-config)#default-router 1.0.0.1
R2(dhcp-config)#lease 1 2 3
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 1.0.0.1 1.0.0.50
R2(config)#exit
R2#
*Aug  3 16:36:39.045: %SYS-5-CONFIG_I: Configured from console by console
R2#sh ip dhcp
% Incomplete command.

R2#sh ip
% Incomplete command.

R2#sh ip binding
^
% Invalid input detected at '^' marker.


R2#
```

```
PNET R4
R4#sh ip int brief
Interface IP-Address OK? Method Status Protocol
Ethernet0/0 222.215.0.2 YES TFTP up up
Ethernet0/1 129.23.0.1 YES TFTP up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down

R4#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R4(config)#int e0/1
R4(config-if)#ip helper-add 222.215.0.1
R4(config-if)#exit
R4(config)#exit
R4#exit
```

```
R5
R5#sh ip int brief
Interface IP-Address OK? Method Status Protocol
Ethernet0/0 62.0.0.2 YES TFTP up up
Ethernet0/1 212.25.0.1 YES TFTP up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down

R5#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R5(config)#int e0/1
R5(config-if)#ip helper-add 62.0.0.1
R5(config-if)#exit
R5(config)#exit
R5#exit
```



PNETLab | Topology

labs.surennetwork.com/legacy/topology

PNETLab | Labs S... Suren Network | Lea...

SUREN NETWORK
PLAY WITH TECHNOLOGIES

QEMU (Win-1)

```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 1.0.0.51
    Subnet Mask . . . . . : 255.0.0.0
    Default Gateway . . . . . : 1.0.0.1

C:\Documents and Settings\user>
```

QEMU (Win-2)

```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 29.0.0.51
    Subnet Mask . . . . . : 255.0.0.0
    Default Gateway . . . . . : 29.0.0.1

C:\Documents and Settings\user>
```

QEMU (Win-3)

```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 129.23.0.51
    Subnet Mask . . . . . : 255.255.0.0
    Default Gateway . . . . . : 129.23.0.1

C:\Documents and Settings\user>
```

QEMU (Win-4)

```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 212.25.0.51
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 212.25.0.1

C:\Documents and Settings\user>

Network Connections



File Edit View Favorites Tools Advanced Help



Back Forward Stop Search Folders



Address



Network



Create New Connection  
Set Up Off-Net Connection  
Change Adapter Settings  
Dial-Up Connections  
Remote Auto Connections  
View Connection Status  
Change Adapter Settings



Physical 01 : 00 : 00 START


```