





```
R1
!
!
!
!
!
ip dhcp excluded-address 50.0.0.1 50.0.0.50
ip dhcp excluded-address 192.168.2.1 192.168.2.50
!
ip dhcp pool HR
network 50.0.0.0 255.0.0.0
default-router 50.0.0.1
dns-server 8.8.8.8
lease 1 2 3
!
ip dhcp pool SALES
network 192.168.2.0 255.255.255.0
default-router 192.168.2.1
dns-server 8.8.8.8
lease 1 2 3
!
!
!
--More--
```

```
R2
ip forward-protocol nd
!
!
no ip http server
no ip http secure-server
ip route 50.0.0.0 255.0.0.0 172.16.0.1
!
ip v6 ioam timestamp
!
!
R2#sh ip int brief
```

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	192.168.2.1	YES	manual	up	up
Ethernet0/1	172.16.0.2	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTF	down	down
Ethernet0/3	unassigned	YES	TFTF	down	down



QEMU (Win)

My Documents

My Computers

My Network Places

Recycle Bin

Internet Explorer

Cisco ASDM-1...

Old Java Applet

PuTTY

Ittd32

Start

```
ex C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600.1]
(C) Copyright 1985-2001 Microsoft Corp.
C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address . . . . . : 192.168.2.52
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 192.168.2.1

C:\Documents and Settings\user>
```


VPC-4


```
VPC-4>
VPC-4> ip dhcp
DORA IP 192.168.2.51/24 GW 192.168.2.1

VPC-4> sh ip

PuTTY
NAME       : VPC-4[1]
IE/MA3K    : 192.168.2.51/24
GATEWAY    : 192.168.2.1
DNS        : 8.8.8.8
DHCP SERVER: 172.16.0.1
DHCP LEASE : 93744, 93780/46890/82054
MAC        : 00:50:79:66:68:97
I,PORT     : 20000
RHOST:PORT : 127.0.0.1:30000
MTU        : 1500

VPC-4>
```





```
Press '?' to get help.

Executing the startup file

VPC-1>
VPC-1> ip dhcp
DDORA IP 50.0.0.51/8 GW 50.0.0.1

VPC-1> sh ip

NAME          : VPC-1[1]
IP/MASK       : 50.0.0.51/8
GATEWAY       : 50.0.0.1
DNS           : 8.8.8.8
DHCP SERVER   : 50.0.0.1
DHCP LEASE    : 93770, 93780/46890/82054
MAC           : 00:50:79:66:68:95
LPORT         : 20000
RHOST:PORT    : 127.0.0.1:30000
MTU           : 1500

VPC-1> █
```

```
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.0.52/8 GW 50.0.0.1

VPC-2> sh ip

NAME          : VPC-2[1]
IP/MASK       : 50.0.0.52/8
GATEWAY       : 50.0.0.1
DNS           : 8.8.8.8
DHCP SERVER   : 50.0.0.1
DHCP LEASE    : 93778, 93780/46890/82054
MAC           : 00:50:79:66:68:96
LPORT        : 20000
RHOST:PORT    : 127.0.0.1:30000
MTU           : 1500

VPC-2>
```