

0. 安装拼音输入法


`sudo apt update`

`sudo apt install ibus-pinyin`


安装完重启

1. 加入中文输入法


点击右上角，打开 settings，选择 region&language，添加新的输入源，如图




点击“+”号，然后点击 other，等待一会，然后找到 chinese (pinyin)，添加。如图：



添加好之后右上角就可以选择输入法了，如图：




实际效果：




2. 安装中文

这里用的是配置好的做一些示例。打开系统设置，找到 region and language，然后点击这里，如图：



然后点击添加或删除语言，如下图：



找到 chinese(simplified)勾选安装，点击应用之后回到上图的界面，点击 应用到整个系统。地区格式可以不弄，然后重启。

Ubuntu 使用 locale 来管理系统的语言和字符集设置。要修改字符集为中文 (UTF-8)，需要生成中文的 locale 设置。打开终端并编辑 locale 配置文件：

```
sudo vim /etc/default/locale
```

修改内容为：

```
LANGUAGE="zh_CN.UTF-8"
```

```
LANG="zh_CN.UTF-8"
```


修改完成后运行以下命令以生成中文 locale:

```
sudo locale-gen zh_CN.UTF-8
```

更新 locale 配置:

```
sudo update-locale
```

现在/etc/default/locale 文件应该是这样的:

A terminal window showing the command 'cat /etc/default/locale' and its output. The output lists various locale settings, all set to 'zh_CN.UTF-8'.

```
cat@lubancat:~$ cat /etc/default/locale
# File generated by update-locale
LANGUAGE="zh_CN.UTF-8"
LANG="zh_CN.UTF-8"
LC_NUMERIC="zh_CN.UTF-8"
LC_TIME="zh_CN.UTF-8"
LC_MONETARY="zh_CN.UTF-8"
LC_PAPER="zh_CN.UTF-8"
LC_IDENTIFICATION="zh_CN.UTF-8"
LC_NAME="zh_CN.UTF-8"
LC_ADDRESS="zh_CN.UTF-8"
LC_TELEPHONE="zh_CN.UTF-8"
LC_MEASUREMENT="zh_CN.UTF-8"
```

然后重启就行.