

AWS EC2 Windows Instance – Creation and Connection using RDP

Task:

Create an EC2 instance using Windows OS and connect to it using Remote Desktop Protocol (RDP).

(a) Steps to Create Windows EC2 Instance:

1. Login to AWS Management Console

- Open <https://aws.amazon.com/>
- Click **Sign In** and enter credentials.

2. Open EC2 Dashboard

- Search for **EC2** in the services menu
- Click on **EC2 Dashboard**

3. Launch Instance

- Click **Launch Instance**

4. Enter Instance Name

- Example: MyWindowsServer

5. Choose Operating System (AMI)

- Select **Microsoft Windows Server 2019/2022 Base**

6. Choose Instance Type

- Select **t2.micro** (Free Tier Eligible, if available)

7. Create Key Pair

- Click **Create new key pair**
- Name: winkey
- Format: .pem
- Download and save the file

8. Configure Network Settings

- Allow **RDP (Port 3389)**
- Source: Anywhere (0.0.0.0/0) for testing

9. Configure Storage

- Default: 30 GB (Windows requires more storage)

10. Launch Instance

- Click **Launch Instance**
- Wait until instance state shows **Running**

11. Get Public IP

- Select instance → Copy **Public IPv4 address**
- Example: 13.233.120.45

(b) Steps to Connect Using RDP:

1. Get Administrator Password

- Select instance → Click **Connect**
- Go to **RDP Client** tab
- Click **Get Password**
- Upload `winkey.pem`
- Click **Decrypt Password**
- Copy the username (Administrator) and password

2. Open Remote Desktop Connection

- Press `Win + R`
- Type `mstsc` and press Enter

3. Enter IP Address

- In Computer field, type:
13.233.120.45 (example)

4. Login Credentials

- Username: Administrator
- Password: (decrypted password)

5. Connect

- Click **Connect**
- Accept security certificate if prompted

Example Summary:

- Instance Name: MyWindowsServer
- OS: Windows Server 2022
- Instance Type: t2.micro
- Key Pair: winkey.pem
- Public IP: 13.233.120.45

Result:

- Windows EC2 instance created successfully.
- Connected to instance using Remote Desktop (RDP).
-