




Microprocessor 8085 - [Code Editor]
File Edit View Converter Options Simulate Help
Microprocessor 8085 Simulator Software Kit 1.0
Ln 19, Col 9
TStates : 218 | MCycles : 65 | Time of Execution : 218 µs
Flags : S Z AC P CY
General Regs.: A 01 B C 00 01 D E 34 12 H L 45 13 M 78 SP 0000 PC 8000
LHLD 4510h
XCHG
LHLD 4512h
MVI C 00h
DAD D
JNC SKIP
INR C
SKIP: SHLD 4514h
MOV A C
STA 4516h
MVI C 00h
LDA 4510h
LXI H 4512h
SUB M
STA 4518h
LDA 4511h
INX H
SBB M
STA 4519h
JNC STORE
INR C
STORE: MOV A C
STA 451Ah
HLT
Starting Address : 8000
Comments :
User Data Grid
Address Data
4510 12
4511 34
4512 56
4513 78
4514 68
4515 AC
4516 00
4517 00
4518 BC
4519 BB
451A 01
451B 00
Hex Code Grid
Address Data
8000 2A
8001 10
8002 45
8003 EB
8004 2A
8005 12
8006 45
8007 0E
8008 00
8009 19
800A D2
800B 0E
800C 80
800D 0C
800E 22
800F 14
8010 45
1.Data Transfer Group :
MOV MVI LDA STA
LHLD SHLD LXI XCHG
LDAX STAX IN OUT
2.Arithmetic Group :
ADD ADI ADC ACI
SUB SUI SBB SBI
INR DCR INX DCX
DAA
DAD
3.Logical Group :
ANA ANI XRA XRI CMA
ORA ORI CMP CPI CMC
RLC RRC RAL RAR STC
4.Branch and Machine Control Group
JMP J_ CALL C_
RET R_ EI DI PUSH
PCHL RST RIM SIM POP
XTHL SPHL NOP HLT
Auto Insert
Insert
Cancel
Instruction Information :
RETurn unconditionally
34°C
Mostly sunny
Search
ENG
US
13:41
12-10-2026


Microprocessor 8085 - [Code Editor]
File Edit View Converter Options Simulate
Microprocessor 8085 Simulator Software Kit 1.0
Ln 16, Col 6
TStates : 224 | MCycles : 65 | Time of Execution : 224 µs
Flags : S Z AC P CY
General Regs.: A 14 B C 7A 00 D E 00 00 H L 22 14 M 00 SP 47FF PC 8000
LXI SP 47FFh
LXI H 4500h
MOV A M
INX H
MOV B M
ADD B
PUSH PSW
STA 4502h
MVI A 00h
ACI 00h
STA 4502h
POP H
MOV A L
STA 4503h
LDA 4500h
SUB B
PUSH PSW
STA 4504h
MVI A 00h
ACI 00h
STA 4506h
POP H
MOV A L
STA 4507h
HLT
Starting Address : 8000
Comments :
User Data Grid
Address Data
4500 9C
4501 7A
4502 01
4503 11
4504 22
4505 00
4506 00
4507 14
Hex Code Grid
Address Data
8000 31
8001 FF
8002 47
8003 21
8004 00
8005 45
8006 7E
8007 23
8008 46
8009 80
800A F5
800B 32
800C 02
800D 45
800E 3E
800F 00
8010 CE
8011 00
1.Data Transfer Group :
MOV MVI LDA STA
LHLD SHLD LXI XCHG
LDAX STAX IN OUT
2.Arithmetic Group :
ADD ADI ADC ACI
SUB SUI SBB SBI
INR DCR INX DCX
DAA
DAD
3.Logical Group :
ANA ANI XRA XRI CMA
ORA ORI CMP CPI CMC
RLC RRC RAL RAR STC
4.Branch and Machine Control Group
JMP J_ CALL C_
RET R_ EI DI PUSH
PCHL RST RIM SIM POP
XTHL SPHL NOP HLT
Auto Insert
Insert
Cancel
Instruction Information :
Code Pad
34°C
Mostly sunny
Search
ENG
US
14:02
12-10-2026


Microprocessor 8085 - [Code Editor]
File Edit View Converter Options Simulate Help
Microprocessor 8085 Simulator Software Kit 1.0
Ln 25, Col 4
TStates : 861 | MCycles : 243 | Time of Execution : 861 µs
Flags : S Z AC P CY
General Regs.: A 14 B 05 C 14 D 00 E 12 H 00 L 5A M 00 SP 0000 PC 8000
LDA 4520h
MOV E A
MVI D 00h
LDA 4521h
MOV C A
LXI H 0000h
ORA A
JZ STORE
LOOP: DAD D
DCR C
JNZ LOOP
STORE: SHLD 4522h
LDA 4525h
MOV B A
LDA 4524h
MVI C 00h
NEXT: CMP B
JC DONE
SUB B
INR C
JMP NEXT
DONE: STA 4527h
MOV A C
STA 4526h
HLT
Starting Address : 8000
Comments :
User Data Grid
Address Data
4520 12
4521 05
4522 5A
4523 00
4524 64
4525 05
4526 14
4527 00
Hex Code Grid
Address Data
8000 3A
8001 20
8002 45
8003 5F
8004 16
8005 00
8006 3A
8007 21
8008 45
8009 4F
800A 21
800B 00
800C 00
800D B7
800E CA
800F 16
8010 80
8011 19
1.Data Transfer Group :
MOV MVI LDA STA
LHLD SHLD LXI XCHG
LDAX STAX IN OUT
2.Arithmetic Group :
ADD ADI ADC ACI
SUB SUI SBB SBI
INR DCR INX DCX
DAA
DAD
3.Logical Group :
ANA ANI XRA XRI CMA
ORA ORI CMP CPI CMC
RLC RRC RAL RAR STC
4.Branch and Machine Control Group
JMP J_ CALL C_
RET R_ EI DI PUSH
PCHL RST RIM SIM POP
XTHL SPHL NOP HLT
Auto Insert
Insert
Cancel
Instruction Information :
Code Pad
34°C
Mostly sunny
Search
ENG
US
14:15
12-10-2026


Microprocessor 8085 - [Code Editor]
File Edit View Converter Options Simulate Help
Microprocessor 8085 Simulator Software Kit 1.0
Ln 23, Col 18
TStates : 1712886 | MCycles : 470002 | Time of Execution : 1712886 µs
Flags : S Z AC P CY
General Regs.: A DC B 00 C 02 D 34 E 12 H 00 L 02 M 00 SP 47FF PC 8000
LXI SP 47FFh
LHLD 4530h
XCHG
LHLD 4532h
MOV B H
MOV C L
LXI H 0000h
SHLD 4536h
MOV A B
ORA C
JZ STORE
MLOOP: DAD D
JNC NOCY
PUSH H
LHLD 4536h
INX H
SHLD 4536h
POP H
NOCY: DCX B
MOV A B
ORA C
JNZ MLOOP
STORE: SHLD 4534h
LHLD 4538h
LXI B 0000h
DLOOP: MOV A L
SUB E
MOV L A
MOV A H
SBB D
MOV H A
Starting Address : 8000
Comments :
User Data Grid
Address Data
4530 12
4531 34
4532 56
4533 78
4534 0C
4535 EE
4536 79
4537 18
4538 56
4539 78
453A 12
453B 34
453C 02
453D 00
453E 32
Hex Code Grid
Address Data
8000 31
8001 FF
8002 47
8003 2A
8004 30
8005 45
8006 EB
8007 2A
8008 32
8009 45
800A 44
800B 4D
800C 21
800D 00
800E 00
800F 22
8010 36
8011 45
1.Data Transfer Group :
MOV MVI LDA STA
LHLD SHLD LXI XCHG
LDAX STAX IN OUT
2.Arithmetic Group :
ADD ADI ADC ACI
SUB SUI SBB SBI
INR DCR INX DCX
DAA
DAD
3.Logical Group :
ANA ANI XRA XRI CMA
ORA ORI CMP CPI CMC
RLC RRC RAL RAR STC
4.Branch and Machine Control Group
JMP J_ CALL C_
RET R_ EI DI PUSH
PCHL RST RIM SIM POP
XTHL SPHL NOP HLT
Auto Insert
Insert
Cancel
Instruction Information :
Code Pad
34°C
Sunny
Search
ENG
US
14:31
12-10-2026