

Install Hyper-V

Applies to:  [Windows Server 2025](#),  [Windows Server 2022](#),  [Windows Server 2019](#),  [Windows Server 2016](#),  [Windows 11](#),  [Windows 10](#),  [Azure Local 2311.2 and later](#)

This article shows how to install Hyper-V in **Windows** and **Windows Server**. Follow the set of instructions that fit your needs.

Enable Hyper-V to create virtual machines on Windows. Hyper-V can be enabled in many ways including using the **Windows control panel**, **PowerShell**, or using the **Deployment Imaging Servicing and Management tool (DISM)**. This article walks through each option.

ⓘ Note

Hyper-V is built into Windows as an optional feature--there's no Hyper-V download.

Check requirements for Windows

- Windows 10 (Pro or Enterprise), or Windows 11 (Pro or Enterprise)
- 64-bit Processor with Second Level Address Translation (SLAT).
- CPU support for VM Monitor Mode Extension (VT-c on Intel CPUs).
- Minimum of 4-GB memory.

ⓘ Note

The Hyper-V role **can't** be installed on Windows 10 Home or Windows 11 Home.

For more information and troubleshooting, see [Windows Hyper-V System Requirements](#).

Enable Hyper-V

PowerShell

To enable Hyper-V on Windows using PowerShell:

1. On the Windows desktop, select the Start button and type any part of the name **Windows PowerShell**.
2. Right-click Windows PowerShell and select **Run as Administrator**.


Important

You must run PowerShell as an Administrator, or the commands fail.

3. Run the following command:

PowerShell

```
Enable-WindowsOptionalFeature -Online -FeatureName Microsoft-Hyper-V -All
```



The screenshot shows a Windows PowerShell window titled "Administrator: Windows PowerShell". The text inside the window reads: "Windows PowerShell", "Copyright (C) Microsoft Corporation. All rights reserved.", "Install the latest PowerShell for new features and improvements! https://aka.ms/PSWindows", "PS C:\WINDOWS\system32> Enable-WindowsOptionalFeature -Online -FeatureName Microsoft-Hyper-V -All", "Do you want to restart the computer to complete this operation now?", "[Y] Yes [N] No [?] Help (default is 'Y'): Y".

4. Enter **Y** to have the computer restart to complete the installation.

To enable the Hyper-V role on Windows using DISM:

The Deployment Image Servicing and Management tool (DISM) helps configure Windows and Windows images. Among its many applications, DISM can enable Windows features while the operating system is running.


1. On the Windows desktop, select the Start button and type any part of the name

Windows PowerShell.

2. Right-click Windows PowerShell and select **Run as Administrator**.
3. Type the following command:

PowerShell

```
DISM /Online /Enable-Feature /All /FeatureName:Microsoft-Hyper-V
```



```
Administrator: Windows PowerShell
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.

Install the latest PowerShell for new features and improvements! https://aka.ms/PSWindows

PS C:\WINDOWS\system32> DISM /Online /Enable-Feature /All /FeatureName:Microsoft-Hyper-V

Deployment Image Servicing and Management tool
Version: 10.0.26100.1150

Image Version: 10.0.26100.3775

Enabling feature(s)
[=====100.0%=====]
The operation completed successfully.
PS C:\WINDOWS\system32>
```

4. You see that the feature is enabled and that "The operation completed successfully."

For more information about DISM, see the [DISM Technical Reference](#).

Next step

- [Create a virtual machine in Hyper-V](#)

Last updated on 05/26/2025