```
## MySQL LIMIT Clause
         The LIMIT clause is used to specify the number of records to return.
         The LIMIT clause is useful on large tables with thousands of records.
         Returning a large number of records can impact performance.
         Syntax :
              SELECT column_name  FROM table_name WHERE condition LIMIT  ;

              SELECT column_name  FROM table_name WHERE condition LIMIT 3 OFFSET 3;


## MySQL GROUP BY Clause
       The GROUP BY statement groups rows that have the same values into summary rows.
       The GROUP BY statement is often used with aggregate functions (COUNT(), MAX(), MIN(), SUM(),
       AVG()).
       Syntax :
        SELECT column_name FROM table_name GROUP BY column_name

## MySQL Having Clause
        The MySQL HAVING Clause is used to filter grouped rows in a table based on conditions.
        This clause is used with the GROUP BY clause to group the rows based on one or more colum
and then filter them.based on the conditions specified in the HAVING clause.
        So, the HAVING clause must always be followed by the GROUP BY clause.
        The HAVING clause was added to MySQL because the WHERE keyword cannot be used with
aggregate functions such as COUNT(), SUM(), AVG(), etc.
        This clause is similar to the MySQL WHERE clause.
        The difference between both of them is that the WHERE clause filters individual rows in a
table. whereas the HAVING clause filters grouped rows based on conditions.

         Syntax :
               SELECT column1, column2, aggregate_function(column)
               FROM table_name
               GROUP BY column1, column2, ...
               HAVING condition;



## MySQL ALTER Table
   MySQL ALTER statement is used when you want to change the name of your table or any tablefield.
   It is also used to add or delete an existing column in a table.
   The ALTER statement is always used with "ADD", "DROP" and "MODIFY" commands according to the
   situation.

 1) ADD a column in the table
       Syntax:
           ALTER TABLE table_name  ADD new_column_name column_definition  [ FIRST or  AFTER
column_name ];

2) MODIFY column in the table
        The MODIFY command is used to change the column definition of the table.
        Syntax:
            ALTER TABLE table_name  MODIFY column_name column_definition ;

 4) DROP column in table
        Syntax:
           ALTER TABLE table_name  DROP COLUMN column_name;

5) RENAME column in table
          Syntax:
           ALTER TABLE table_name  CHANGE COLUMN old_name  new_name coloumn_decleration

6) RENAME table
         Syntax:
             ALTER TABLE table_name RENAME TO new_table_name;
```