




```
<S1>system-view
```

Enter system view, return user view with Ctrl+Z.

```
[S1]display current-configuration
```

```
#
```

```
sysname S1
```

```
#
```

```
cluster enable
```

```
ntdp enable
```

```
ndp enable
```

```
#
```

```
undo nap slave enable
```

```
#
```

```
drop illegal-mac alarm
```

```
#
```

```
diffserv domain default
#
drop-profile default
#
aaa
authentication-scheme default
authorization-scheme default
accounting-scheme default
domain default
domain default_admin
local-user admin password cipher $K&%QCXM$NYNZPO3JBXBHA!!
local-user admin privilege level 15
local-user admin service-type terminal ssh
#
interface Vlanif1
ip address 192.168.56.11 255.255.255.0
#
interface MEth0/0/1
#
interface GigabitEthernet0/0/1
#
interface GigabitEthernet0/0/2
#
interface GigabitEthernet0/0/3
#
interface GigabitEthernet0/0/4
```

```
#  
  
interface GigabitEthernet0/0/5  
  
#  
  
interface GigabitEthernet0/0/6  
  
#  
  
interface GigabitEthernet0/0/7  
  
#  
  
interface GigabitEthernet0/0/8  
  
#  
  
interface GigabitEthernet0/0/9  
  
#  
  
interface GigabitEthernet0/0/10  
  
#  
  
interface GigabitEthernet0/0/11  
  
#  
  
interface GigabitEthernet0/0/12  
  
#  
  
interface GigabitEthernet0/0/13  
  
#  
  
interface GigabitEthernet0/0/14  
  
#  
  
interface GigabitEthernet0/0/15  
  
#  
  
interface GigabitEthernet0/0/16  
  
#  
  
interface GigabitEthernet0/0/17
```

```
#  
interface GigabitEthernet0/0/18  
#  
interface GigabitEthernet0/0/19  
#  
interface GigabitEthernet0/0/20  
#  
interface GigabitEthernet0/0/21  
#  
interface GigabitEthernet0/0/22  
#  
interface GigabitEthernet0/0/23  
#  
interface GigabitEthernet0/0/24  
#  
interface NULL0  
#  
stelnet server enable  
ssh user admin  
ssh user admin authentication-type password  
ssh user admin service-type stelnet  
#  
user-interface con 0  
user-interface vty 0 4  
authentication-mode aaa  
user privilege level 15
```

```
protocol inbound ssh
```

```
#
```

```
return
```

```
<R1>system-view
```

Enter system view, return user view with Ctrl+Z.

```
[R1]display current-configuration
```

```
#
```

```
sysname R1
```

```
#
```

```
undo nap slave enable
```

```
#
```

```
aaa
```

```
authentication-scheme default
```

```
authorization-scheme default
```

```
accounting-scheme default
```

```
domain default
```

```
domain default_admin
```

```
local-user admin password cipher gH4*"logBI3@9_G-B0Y2"Fu#
```

```
local-user admin service-type terminal ssh
```

```
#
```

```
firewall zone Local
```

```
priority 16
```

```
#
```

```
interface Ethernet0/0/0
```

```
#
```

```
interface Ethernet0/0/1
```

#

interface Serial0/0/0

link-protocol ppp

#

interface Serial0/0/1

link-protocol ppp

#

interface Serial0/0/2

link-protocol ppp

#

interface Serial0/0/3

link-protocol ppp

#

interface GigabitEthernet0/0/0

ip address 192.168.56.10 255.255.255.0

#

interface GigabitEthernet0/0/1

#

interface GigabitEthernet0/0/2

#

interface GigabitEthernet0/0/3

#

wlan

#

interface NULL0

#

```
ip route-static 0.0.0.0 0.0.0.0 192.168.56.11
```

```
#
```

```
stelnet server enable
```

```
ssh user admin
```

```
ssh user admin authentication-type password
```

```
ssh user admin service-type stelnet
```

```
#
```

```
user-interface con 0
```

```
user-interface vty 0 4
```

```
authentication-mode aaa
```

```
user privilege level 15
```

```
protocol inbound ssh
```

```
user-interface vty 16 20
```

```
#
```

```
return
```