NET512 Week 1

```
Press RETURN to get started!


Router>?
Exec commands:
  <1-99>      Session number to resume
  connect     Open a terminal connection
  disable     Turn off privileged commands
  disconnect  Disconnect an existing network connection
  enable      Turn on privileged commands
  exit        Exit from the EXEC
  logout      Exit from the EXEC
  ping        Send echo messages
  resume      Resume an active network connection
  show        Show running system information
  ssh         Open a secure shell client connection
  telnet      Open a telnet connection
  terminal    Set terminal line parameters
  traceroute  Trace route to destination
Router>show version
Cisco IOS XE Software, Version 03.16.05.S - Extended Support Release
Cisco IOS Software, ISR Software (X86_64_LINUX_IOSD-UNIVERSALK9-M), Version Version 15.5 (3)S5,
RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2017 by Cisco Systems, Inc.
Compiled Thu 19-Jan-17 11:24 by mcpre

Cisco IOS-XE software, Copyright (c) 2005-2017 by cisco Systems, Inc.
All rights reserved.  Certain components of Cisco IOS-XE software are
licensed under the GNU General Public License ("GPL") Version 2.0.  The
software code licensed under GPL Version 2.0 is free software that comes
with ABSOLUTELY NO WARRANTY.  You can redistribute and/or modify such
GPL code under the terms of GPL Version 2.0.  For more details, see the
```




```
Router#?
Exec commands:
  <1-99>      Session number to resume
  auto        Exec level Automation
  clear       Reset functions
  clock       Manage the system clock
  configure   Enter configuration mode
  connect     Open a terminal connection
  copy        Copy from one file to another
  debug       Debugging functions (see also 'undebug')
  delete      Delete a file
  dir         List files on a filesystem
  disable     Turn off privileged commands
  disconnect  Disconnect an existing network connection
  enable      Turn on privileged commands
  erase       Erase a filesystem
  exit        Exit from the EXEC
  logout      Exit from the EXEC
  mkdir       Create new directory
  more        Display the contents of a file
  no          Disable debugging informations
  ping        Send echo messages
  reload      Halt and perform a cold restart
```

```
Router#show ?
  aaa                 Show AAA values
  access-lists        List access lists
  arp                 Arp table
  cdp                 CDP information
  class-map           Show QoS Class Map
  clock               Display the system clock
  controllers         Interface controllers status
  crypto              Encryption module
  debugging           State of each debugging option
  dhcp                Dynamic Host Configuration Protocol status
  dot11               IEEE 802.11 show information
  file                Show filesystem information
  flash:              display information about flash: file system
  flow                Flow information
  frame-relay         Frame-Relay information
  history             Display the session command history
  hosts               IP domain-name, lookup style, nameservers, and host table
  interfaces          Interface status and configuration
  ip                  IP information
  ipv6                IPv6 information
  license             Show license information
  line                TTY line information
```

```
Building configuration...

Current configuration : 522 bytes
!
version 15.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname Router
!
!
!
!
!
!
!
ip cef
no ipv6 cef
!
!

Router#show ip interface brief
Interface              IP-Address      OK? Method Status                Protocol
GigabitEthernet0/0/0   unassigned      YES unset  administratively down down
GigabitEthernet0/0/1   unassigned      YES unset  administratively down down
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname R1
R1(config)#exit
R1#
%SYS-5-CONFIG_I: Configured from console by console
copy running-config startup-config
Destination filename [startup-config]?
```

```
%SYS-5-CONFIG_I: Configured from console by console
copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R1#show running-config
Building configuration...

Current configuration : 518 bytes
!
version 15.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R1
!
!
!
!
!
!
!
ip cef
no ipv6 cef
!
!

R1#show startup-config
Using 518 bytes
!
version 15.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
```

```
R1#show startup-config
Using 518 bytes
!
version 15.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R1
!
!
!
!
!
!
!
!
ip cef
no ipv6 cef
!
!
!
!

R1#
```