



STONEWEAVE

Version Control

Installation Guide

Setting up Stoneweave Version Control on Windows

June 2026 V1.0

1. Before You Begin

This guide covers the installation of both the Stoneweave Server and the Stoneweave Client on Windows. No technical background is required - simply follow the steps in order.

What You Will Need

- A PC running Windows 10 or Windows 11 (64-bit)
- The installer file provided by your supplier:
 - Server: PLCVersionControl-Server-Setup.exe
 - Client: PLCVersionControl-Client-Setup.exe
- Standard user account - no administrator rights are required
- Approximately 200 MB of free disk space for the application itself
- A separate location with plenty of free space for your data files and database

2. Installing the Server Application

The Server application hosts the version control system. It must be installed on one PC that is always switched on and reachable by everyone on the network.

Running the Installer

1. Double-click PLCVersionControl-Server-Setup.exe.
2. If a Windows SmartScreen warning appears, click More info then Run anyway.
3. Read and accept the Licence Agreement, then click Next.
4. Choose an installation folder or accept the default, then click Next.

Default location: C:\Users\YourName\AppData\Local\Programs\PLCVersionControl

5. Click Install. The installer copies all files.
6. Click Finish. The application starts automatically.

Note

The installer does not require administrator rights. The application installs into your user profile - no system-wide changes are made.

What Happens After Installation

After the installer finishes, a small Stoneweave icon appears in the Windows system tray (bottom-right corner of the taskbar). The server is now running.

- A browser window opens automatically to <http://127.0.0.1:5000>
- You will see the Stoneweave login page

- Default login: Username admin Password admin

Warning

Change the default password immediately before doing anything else. See Section 4.

3. First-Time Server Setup

Logging In for the First Time

1. Open a web browser and go to `http://127.0.0.1:5000`
2. Enter Username: admin and Password: admin
3. Click Log In.

On first login you will be presented with an End-User Licence Agreement. Read and accept it to continue.

Changing the Admin Password (Required)

1. Click your name in the top-right corner of the screen.
2. Select Profile from the drop-down menu.
3. Click Edit Profile.
4. Enter a new password - it must be at least 12 characters long.
5. Confirm the new password and click Save.

Tip

Use a strong password with a mix of letters, numbers, and symbols. The system will reject common passwords and passwords shorter than 12 characters.

Choosing Where to Store Your Files

By default, all data is stored in a folder called `plvc_data` inside your user profile. For most installations you will want to move this to a dedicated location such as a fast internal drive or a network share.

1. In the left sidebar, click Settings.
2. Select the Storage tab.
3. Enter the full path to your chosen data folder (e.g. `D:\StoneweaveData`).
4. Click Save. The server restarts and uses the new location.

Warning

If you change the storage location after files have already been added, you must manually move the existing data folder to the new path before restarting.

Note

Choose a location with plenty of free space. Each version of every file is stored as a separate full copy.

4. Setting Up Network Access

By default, the server is only accessible from the PC it is installed on. To allow colleagues to connect from their workstations, you need to share the local network (LAN) address.

Finding the LAN Address

1. Right-click the Stoneweave icon in the system tray (bottom-right of the taskbar).
2. The menu shows the LAN address - for example: `http://192.168.1.105:5000` - note this down.

Alternatively: open Command Prompt and run `ipconfig` - look for the IPv4 Address under your active network adapter.

Tip

Share this address with your colleagues. Tell them: open a web browser and go to `http://192.168.1.105:5000` (replace with your actual IP address).

System Tray Icon

Right-clicking the Stoneweave tray icon gives you the following options:

- Open Browser - opens the application in your default browser
- Copy LAN URL - copies the network address to the clipboard so you can paste it into an email or message
- Exit - stops the server. All connected users will lose access until you restart it.

Warning

Only exit the server when all users have finished working. Restarting is instant.

Stopping and Starting the Server

- To stop: right-click the tray icon → Exit
- To start: double-click the desktop shortcut, or find Stoneweave Version Control in the Start Menu

5. Setting Up HTTPS (Recommended)

By default the application uses plain HTTP. Enabling HTTPS encrypts all traffic between the server and users' browsers. This is strongly recommended for any team environment.

Automatic Setup (Recommended)

1. In the sidebar, click Settings.
2. Select the Security tab, then the HTTPS / TLS sub-tab.

3. Click Setup HTTPS Automatically.
4. The server restarts with HTTPS enabled. The address becomes `https://192.168.1.105:5000`

Note

Browsers will show a security warning the first time each user connects. This is expected with a self-signed certificate. Click Advanced then Proceed to continue.

Manual Setup

If you have your own SSL certificate files (.crt and .key), enter the full paths to both files in the Certificate Path and Key Path fields, then click Save.

6. Installing the Client Application

The Client application is a small launcher for users who connect from their own workstations. It stores the server address and opens the correct URL in a browser with a single click.

Before Installing on Each PC

- Installer file: PLCVersionControl-Client-Setup.exe (Available to download from the Stoneweave Website)
- The server address (e.g. `http://192.168.1.105:5000` or `https://192.168.1.105:5000`)

Running the Client Installer

1. Copy the installer to the user's PC and double-click it.
2. If a Windows SmartScreen warning appears, click More info then Run anyway.
3. Accept the Licence Agreement and click Next.
4. When prompted, enter the server address your admin gave you.
5. Click Install, then Finish.

A desktop shortcut and Start Menu entry are created. Double-clicking the shortcut opens Stoneweave in the user's default browser.

Tip

No technical knowledge is needed on the client PC. Standard user rights are sufficient - no administrator permissions are required.

Supported Browsers

Browser	Support	Notes
Microsoft Edge	Recommended	Best experience on Windows
Google Chrome	Supported	
Mozilla Firefox	Supported	
Safari	Supported	macOS / iOS

Internet Explorer	Not supported	Use Edge instead
-------------------	---------------	------------------

7. Adding User Accounts

After completing setup, create a personal account for each person who will use the system. Do not share the admin account.

1. In the sidebar, click Users.
2. Click Add User.
3. Enter their name, username, email address, and an initial password.
4. Select their role (see table below) and click Save.

Role	What They Can Do
Operator	Browse files, check out and check in files, view audit log
Supervisor	All of the above, plus revert versions and manage projects and areas
Admin	Full access - users, settings, backups, and all supervisor actions

Tip

Give each user their username, password, and the server address. They can change their own password after first login.

8. Where Your Data Is Stored

All Stoneweave data lives inside one folder - the data directory. You can see the exact path at any time in Settings → Storage.

- plcvc.db - the database containing all projects, files, versions, users, and the audit log
- uploads/ - all stored file versions (each version is a separate file copy)

Warning

Back up the entire data directory regularly. The Backup page (sidebar → Backup) shows the exact paths and provides backup tools.

9. Software Updates

Stoneweave checks for updates automatically once per hour. When a new version is available:

- Admins see a banner at the top of every page: 'Update available - vX.X.X'
- Click View release notes to see what has changed
- Go to Settings → Updates and click Install Update
- The installer runs silently in the background, the server restarts, and the application reopens automatically

Note

The update process takes under a minute. The server is briefly unavailable while it restarts.

10. Uninstalling

1. Right-click the tray icon and click Exit to stop the server.
2. Open Windows Settings → Apps → Installed apps.
3. Find Stoneweave Version Control and click Uninstall.

Note

Uninstalling the application does NOT delete your data folder. Your database and file versions are preserved. Delete the data directory manually if you want to remove all data.