



STONEWEAVE

Version Control

Licensing Guide

Understanding your licence and Premium features

June 2026 V1.0

Early Access Notice

Note

Stoneweave Version Control is currently in Early Access. The core version control system is fully functional and ready for daily use. The Premium tier is under active development - Premium features listed in this guide are planned and will be made available in upcoming releases.

All registered users will be notified when Premium features are activated. Updates are delivered automatically through the built-in update system - no manual action is required.

1. Overview

Stoneweave Version Control is available in two tiers:

Tier	Summary
Free	Fully functional for small teams. Includes all core version control features with sensible limits on projects, files, and users. No licence key required.
Premium	Removes all limits and adds advanced features including automated backup, enhanced security (2FA, LDAP/AD), REST API access, SMTP email, and richer export options. Premium features are being progressively activated - see the Early Access notice above.

Licences are perpetual or time-limited depending on your agreement. Licence validation is performed entirely offline - no internet connection is required after activation.

2. Free vs Premium - Feature Comparison

Feature	Free	Premium
Projects	Up to 3	Unlimited
Files per project	Up to 25	Unlimited
Versions per file	Up to 10	Unlimited
Users	Up to 5	Unlimited
File upload size	100 MB	1 GB
Area nesting depth	1 level	3 levels
Change documents per version	1	Up to 10
Change document combined size	10 MB	Unlimited
Export audit log	CSV only	CSV, Excel, PDF
Export file list	CSV only	CSV, Excel, PDF
Two-Factor Authentication (2FA)	No	Yes (planned)
REST API access	No	Yes (planned)
API Key management	No	Yes (planned)
Web UI backup download	No	Yes (planned)
Automatic scheduled backup	No	Yes (planned)
SMTP email / password reset	No	Yes (planned)
Active Directory (LDAP)	No	Yes (planned)

Note

Features marked 'planned' are in active development and will be enabled in a future update. All other features are available today.

3. Activating Your Licence

1. Log in as an admin and click Settings in the left sidebar.
2. Select the License tab.
3. Paste your licence key into the input field.
4. Click Activate.

Tip

The tier badge changes to Premium immediately. No server restart is required.

Warning

Licences are bound to the specific machine they are first activated on. The Machine ID is displayed on the License tab. Your supplier needs this Machine ID when issuing your licence. To move the server to a different PC, contact your supplier to request a transfer.

Finding Your Machine ID

1. Go to Settings → License.
2. Your Machine ID is shown in the Machine ID field.
3. Click the copy button to copy it to the clipboard.

4. What Happens When a Licence Expires

When a Premium licence expires, the system returns to the Free tier. Your data is never deleted or modified - you simply cannot add more content if you are already over the Free tier limits.

- All existing projects, files, and versions remain fully accessible
- You cannot add new files if any project has more than 25, or add new projects if you already have more than 3
- Renew by activating a new licence key via Settings → License

Tip

Contact your supplier before expiry to avoid any disruption to your team.

5. Two-Factor Authentication (Premium - Planned)

Note

This feature is under development and will be available in a future update.

Two-Factor Authentication (2FA) adds a second verification step at login. After entering their password, users must also enter a 6-digit code from an authenticator app on their phone. This significantly reduces the risk of unauthorised access.

Compatible Authenticator Apps

- Google Authenticator
- Microsoft Authenticator
- Authy
- Any TOTP-compatible authenticator app

How 2FA Will Work

1. Go to Settings → Security → 2FA & API Keys.
2. Click Set Up 2FA.
3. Scan the QR code with your authenticator app.
4. Enter the 6-digit code shown in the app to confirm setup.
5. Save the backup codes in a safe place.
6. Click Enable.

Warning

Save your backup codes before closing the setup page. If you lose your phone, backup codes are the only way to regain access to your account.

6. REST API (Premium - Planned)

Note

This feature is under development and will be available in a future update.

The REST API allows you to integrate Stoneweave with other systems - SCADA platforms, MES, scripts, or custom tooling - without using the browser interface.

Getting an API Key

1. Go to Settings → Security → 2FA & API Keys.
2. Click Generate API Key.
3. Copy the key immediately and store it securely.

Warning

Treat the API key like a password. Do not share it or commit it to source control.

API Endpoints

Method	Endpoint	Description
GET	/api/v1/projects	List all projects
GET	/api/v1/files	List all files (optional: ?project_id=X)
GET	/api/v1/files/{id}	Get details of a single file
POST	/api/v1/files/{id}/checkout	Check out a file (body: reason)
POST	/api/v1/files/{id}/checkin	Check in a file (multipart: file + description)

Authentication Header

`Authorization: Bearer YOUR_API_KEY`

7. Backup & Restore

Manual Backup (All Tiers - Available Now)

You can create a manual backup at any time by copying the data folder while the server is stopped:

1. Right-click the Stoneweave tray icon and click Exit to stop the server.
2. Copy the entire data folder to a safe location (network share, USB drive, cloud storage, etc.).
3. Restart the server.

Note

The data folder path is shown in Settings → Storage.

Web UI Backup Download (Premium - Planned)

Note

This feature is under development and will be available in a future update.

When available, Premium users can download a complete backup ZIP directly from the browser without stopping the server:

1. Click Backup in the left sidebar.
2. Click Download Backup.
3. A ZIP file containing the database and all file versions is created and downloaded.

Automatic Scheduled Backup (Premium - Planned)

Note

This feature is under development and will be available in a future update.

When available, Stoneweave will automatically create a dated backup ZIP on a configurable schedule. Options include daily, weekly, fortnightly, monthly, and yearly. You choose the destination folder, time of day, and day of week or month.

Restoring from Backup

1. Stop the server - right-click the tray icon → Exit.
2. Extract the backup ZIP.
3. Replace `plcvc.db` in the data directory with the one from the backup.
4. Copy the `uploads/` folder from the backup into the data directory, overwriting existing content.
5. Restart the server - all data will be restored.

Warning

Restoring overwrites all data since the backup was taken. Any check-ins or changes made after the backup date will be lost.

8. SMTP Email / Password Reset (Premium - Planned)

Note

This feature is under development and will be available in a future update.

When available, admins will be able to configure an outgoing email server (SMTP) to enable automated password reset emails. Users who forget their password can request a reset link sent to their registered email address - no admin intervention required.

Configuration will be found in Settings → Security → Email (SMTP). You will need your SMTP server hostname, port, username, password, and sender address.

9. Active Directory / LDAP Integration (Premium - Planned)

Note

This feature is under development and will be available in a future update.

When available, Stoneweave will allow users to log in with their existing Windows Active Directory (AD) credentials. Admins will not need to manage separate passwords for each user.

Configuration will be found in Settings → Security → Active Directory. You will need your AD server address, a service account with read permissions, and the Base Distinguished Name (DN) for your directory.

10. Excel and PDF Exports (Premium)

Premium users can export the Audit Log and Files list to Excel (.xlsx) or PDF in addition to the standard CSV format.

1. Go to the Audit Log or Files page.
2. Click the Export button at the top of the page.
3. Select CSV (all tiers), Excel (Premium), or PDF (Premium).

Tip

CSV export is available to all users at no cost.

11. Frequently Asked Questions

Question	Answer
Do I need an internet connection to run Stoneweave?	No. The server runs entirely on your local network. Licence validation is offline. The update check fetches from the internet but this is optional and can be disabled.
Does my data survive if the licence expires?	Yes - nothing is ever deleted. You return to Free tier limits but all existing content remains fully accessible.
Can I move the server to a different PC?	Yes. Copy the data folder to the new PC, reinstall the server application, and restore the data. If your licence is machine-bound, contact your supplier for a transfer before moving.
How many users can I have on the Free tier?	Up to 5 active user accounts.
Can I free up user slots by disabling accounts?	Yes - disabling an account frees its slot while preserving the full audit trail history.
Can I trial Premium features?	Contact your supplier for a time-limited trial licence key.
When will Premium features be available?	We are actively developing the Premium tier. Updates are delivered automatically - you will see a notification in the app when new features are enabled.
Is there a limit on file types?	Some potentially dangerous file types (.exe, .bat, etc.) are blocked by default. Admins can configure allowed file types in Settings → Categories → File Types.