

a) Creating First Linux Instance


Step 1:




Step 2:


Create key pair
Key pair name
Key pairs allow you to connect to your instance securely.
sahasra1819
The name can include up to 255 ASCII characters. It can't include leading or trailing spaces.
Key pair type
RSA
RSA encrypted private and public key pair
ED25519
ED25519 encrypted private and public key pair
Private key file format
.pem
For use with OpenSSH
.ppk
For use with PuTTY
When prompted, store the private key in a secure and accessible location on your computer. You will need it later to connect to your instance. Learn more
Cancel
Create key pair


Step 3:


Network settings Info
Network Info
vpc-0f35788e9554bdf79
Subnet Info
No preference (Default subnet in any availability zone)
Auto-assign public IP Info
Enable
Firewall (security groups) Info
A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.
Create security group
Select existing security group
We'll create a new security group called 'launch-wizard-1' with the following rules:
Allow SSH traffic from
Helps you connect to your instance
My IP
103.125.161.178/32
Allow HTTPS traffic from the internet
To set up an endpoint, for example when creating a web server
Allow HTTP traffic from the internet
To set up an endpoint, for example when creating a web server
Rules with source of 0.0.0.0/0 allow all IP addresses to access your instance. We recommend setting security group rules to allow access from known IP addresses only.


Step 4:


Configure storage Info
Adv
1x
8
GiB
gp3
Root volume, 3000 IOPS, Not encrypted
Add new volume
Click refresh to view backup information
The tags that you assign determine whether the instance will be backed up by any Data Lifecycle Manager policies.
File systems
S3 Files - new
EFS
FSx
None
Success
Successfully initiated launch of instance (i-009e5c32fb189d0db)
Launch log


Step 5:


aws
Search
[Alt+S]
Europe (Stockholm)
sahasrasagi (433617670615)
sahasrasagi
EC2 / Instances
EC2
Dashboard
AWS Global View
Events
Instances
Instances
Instance Types
Launch Templates
Spot Requests
Savings Plans
Reserved Instances
Dedicated Hosts
Instances (1/1) Info
Last updated 1 minute ago
Connect
Instance state
Actions
Launch instances
Saved filter sets
Choose filter set
Filter Instance by attribute or tag (case-sensitive)
Instance state = running
Clear filters
Name
Instance ID
Instance state
Instance type
Status check
Availability Zone
Public IPv4 DNS
sahasra_sagi
i-009e5c32fb189d0db
Running
t3.micro
3/3 checks passed ...
eu-north-1b
ec2-51-20-54-11.eu-north-1.
i-009e5c32fb189d0db (sahasra_sagi)

Step 6:


EC2 / Instances / i-009e5c32fb189d0db / Connect to instance
Instance
i-009e5c32fb189d0db (sahasra_sagi)
State: Running
Status: 3/3 checks passed
VPC
vpc-0f35788e9554bdf79
Subnet
subnet-0b4f805fc0836ef40
Security groups
sg-03a1f936635625d0d (launch-wizard-1)
In web browser
In SSH client
Choose how to connect
Public subnet access
Managed SSH keys
EC2 Instance Connect
Use for instances with public IPs or accessible via standard routing. Requires network connectivity to your instance. Connect using temporary SSH keys managed by AWS.
Private subnet access
Managed SSH keys
EC2 Instance Connect Endpoint
Use for instances in private subnets. Traffic is routed through a VPC endpoint. Connect using temporary SSH keys managed by AWS.
Maximum security
IAM authentication
SSM Session Manager
Uses IAM-based authentication. Connect without SSH keys, bastion hosts, or opening any inbound ports.
Direct
Troubleshoot
EC2 Serial Console
Access your instance's serial port for troubleshooting boot, network, and OS issues. Works without network connectivity. Requires account-level enablement.
Settings
Choose public IP address
IPv4 address (51.20.54.11)
IPv6 address
Username
Enter the username defined in the AMI used to launch the instance. If you didn't define a custom username, use the default username, ec2-user. Read your AMI usage instructions to check if the AMI owner has changed the default AMI username.
ec2-user
Cancel
Connect assist
Connect

Step 7:



eu-north-1.console.aws.amazon.com/ec2-instance-connect/ssh/home?region=eu-north-1&connType=sta
aws
Search
[Alt+S]
Amazon Linux 2023
https://aws.amazon.com/linux/amazon-linux-2023
[ec2-user@ip-172-31-34-2 ~]$

```
  ,     #_
  ~\_  ####_        Amazon Linux 2023
 ~~  \_#####\
 ~~     \###|
 ~~       \#/ ___   https://aws.amazon.com/linux/amazon-linux-2023
  ~~       V~' '->
   ~~~         /
     ~~._.   _/
        _/ _/
      _/m/'
[ec2-user@ip-172-31-34-2 ~]$ ls
[ec2-user@ip-172-31-34-2 ~]$ mkdir test
[ec2-user@ip-172-31-34-2 ~]$ ls
test
[ec2-user@ip-172-31-34-2 ~]$ vi file.txt
[ec2-user@ip-172-31-34-2 ~]$ cat  file.txt
testpage


[ec2-user@ip-172-31-34-2 ~]$
```

b) S3 Bucket Creation and Upload Objects


Step 1:




Step 2:


eu-north-1.console.aws.amazon.com/s3/bucket/create?region=eu-north-1
Ask Google
aws
Search
[Alt+S]
Amazon S3 / Buckets / Create bucket
General configuration
AWS Region
Europe (Stockholm) eu-north-1
Bucket type
Info
General purpose
Recommended for most use cases and access patterns. General purpose buckets are the original S3 bucket type. They allow a mix of storage classes that redundantly store objects across multiple Availability Zones.
Directory
Recommended for low-late
faster processing of data
Bucket namespace
Choose the namespace where you want to create your bucket. Learn more
Global namespace
By default, S3 creates general purpose buckets in the global namespace.
Account Regional namespace (recommended)
General purpose buckets created in your account Regional namespace are unique to your account. These buckets can never be created by another AWS account.
Bucket name
For general purpose buckets in the account Regional namespace, the bucket name is composed of a bucket name prefix and a suffix. AWS adds the suffix to the bucke
can't be edited after the bucket is created.
Bucket name prefix
Account Regional namespac
demobucket1
-433617670615-eu-north-1-a
The bucket name prefix and the account Regional suffix combined must be between 3 and 63 characters long. The specified bucket name prefix must be unique within your account Regional namespace and follow the bucket naming rules .
Full bucket name
demobucket1-433617670615-eu-north-1-an
Copy settings from existing bucket - optional
Only the bucket settings in the following configuration are copied.
Choose bucket


Step 3:


Object Ownership Info
Control ownership of objects written to this bucket from other AWS accounts and the use of access control lists (ACLs). Object ownership determines who can specify access to obje
Object Ownership
ACLs disabled (recommended)
All objects in this bucket are owned by this account. Access to this bucket and its objects is specified using only policies.
ACLs enabled
Objects in this bucket can be owned by other AWS accounts. Access to this bucket and its objects can be specified using ACLs.
Object Ownership
Bucket owner enforced
Block Public Access settings for this bucket
Public access is granted to buckets and objects through access control lists (ACLs), bucket policies, access point policies, or all. In order to ensure that public access to this bucket a
public access. These settings apply only to this bucket and its access points. AWS recommends that you turn on Block all public access, but before applying any of these settings, en
without public access. If you require some level of public access to this bucket or objects within, you can customize the individual settings below to suit your specific storage use ca
Block all public access
Turning this setting on is the same as turning on all four settings below. Each of the following settings are independent of one another.
Block public access to buckets and objects granted through new access control lists (ACLs)
S3 will block public access permissions applied to newly added buckets or objects, and prevent the creation of new public access ACLs for existing buckets and objects. This setting doesn't change an
resources using ACLs.
Block public access to buckets and objects granted through any access control lists (ACLs)
S3 will ignore all ACLs that grant public access to buckets and objects.
Block public access to buckets and objects granted through new public bucket or access point policies
S3 will block new bucket and access point policies that grant public access to buckets and objects. This setting doesn't change any existing policies that allow public access to S3 resources.
Block public and cross-account access to buckets and objects through any public bucket or access point policies
S3 will ignore public and cross-account access for buckets or access points with policies that grant public access to buckets and objects.


Step 4:


Default encryption Info
Server-side encryption is automatically applied to new objects stored in this bucket.
Encryption type Info
Secure your objects with two separate layers of encryption. For details on pricing, see DSSE-KMS pricing on the Storage tab of the Amazon S3 pricing page.
Server-side encryption with Amazon S3 managed keys (SSE-S3)
Server-side encryption with AWS Key Management Service keys (SSE-KMS)
Dual-layer server-side encryption with AWS Key Management Service keys (DSSE-KMS)
Bucket Key
Using an S3 Bucket Key for SSE-KMS reduces encryption costs by lowering calls to AWS KMS. S3 Bucket Keys aren't supported for DSSE-KMS. Learn more
Disable
Enable
Advanced settings
After creating the bucket, you can upload files and folders to the bucket, and configure additional bucket settings.
Cancel
Create bucket


Step 5:


eu-north-1.console.aws.amazon.com/s3/buckets/demobucket1-433617670615-eu-north-1-an?region=eu-n...
aws
Search
[Alt+S]
Amazon S3 / Buckets / demobucket1-433617670615-eu-north-1-an
Successfully created bucket "demobucket1-433617670615-eu-north-1-an"
demobucket1-433617670615-eu-north-1-an Info
Objects
Metadata
Properties
Permissions
Metrics
Management
File systems
Access Points
Objects (0)
Copy S3 URI
Copy URL
Download
Objects are the fundamental entities stored in Amazon S3. You can use Amazon S3 inventory to get a list of all objects in your bucket. For others to acces
more
Find objects by prefix
Name
Type
Last modified
Size
No objects
You don't have any objects in this bucket.
Upload


Step 6:



Upload Info
Add the files and folders you want to upload to S3. To upload a file larger than 160GB, use the AWS CLI, AWS SDKs or Amazon S3 REST API. Learn more
Drag and drop files and folders you want to upload here, or choose Add files or Add folder.
Files and folders (1 total, 1.3 MB)
Remove
Add files
All files and folders in this table will be uploaded.
Find by name
Name
Folder
Type
Size
Handout-CDIS.pdf
-
application/pdf
1.3 MB
Destination Info
Destination
s3://demobucket1-433617670615-eu-north-1-an
Destination details
Bucket settings that impact new objects stored in the specified destination.
Permissions
Grant public access and access to other AWS accounts.
Properties
Specify storage class, encryption settings, tags, and more.
CloudShell
Agent Toolkit for AWS
Feedback
Console Mobile App
© 2026, Amazon Web Services, Inc. or its affiliates.
Privacy
Terms

Step 7:


Amazon S3
Upload succeeded
For more information, see the Files and folders table.
Upload: status
After you navigate away from this page, the following information is no longer available.
Summary
Destination
s3://demobucket1-433617670615-eu-north-1-an
Succeeded
1 file, 1.3 MB (100.00%)
Failed
0 files, 0 B (0%)
Files and folders
Configuration
demobucket1-433617670615-eu-north-1-an
Info
Objects
Metadata
Properties
Permissions
Metrics
Management
File systems
Access Points
Objects (1)
Copy S3 URI
Copy URL
Download
Open
Delete
Objects are the fundamental entities stored in Amazon S3. You can use Amazon S3 inventory to get a list of all objects in your bucket. For others to access your objects, you'll need
more
Find objects by prefix
Name
Type
Last modified
Size
Handout-CDIS.pdf
pdf
November 12, 2026, 11:17:15 (UTC+05:30)
1.3

Bucket with public access:




test-bucket-433617670615-eu-north-1-an.s3.eu-north-1.amazonaws.com/skill1_CDIS.pdf
This XML file does not appear to have any style information associated with it. The document tree is shown below.
<Error>
<Code>AccessDenied</Code>
<Message>Access Denied</Message>
<RequestId>GAZ2TFPQ0YKGZJ1C</RequestId>
<HostId>ixbKNne8M5lHZ6JAI9Yu1V1pyb0P8LXYXqqUVDWObAoEnlw1/FxunQddaCkcqpowwATCXKsy1iY=</HostId>
</Error>