


```
interface Ethernet0/0
ip address 50.0.0.1 255.0.0.0
```

```
interface Ethernet0/1
no ip address
```

```
interface Ethernet0/2
no ip address
```

```
interface Ethernet0/3
no ip address
```

```
ip forward-protocol nd
```

```
no ip http server
no ip http secure-server
```

```
control-plane
```

```
line con 0
exec-timeout 0 0
privilege level 15
logging synchronous
line aux 0
exec-timeout 0 0
privilege level 15
logging synchronous
line vty 0 2
password cisco
login
transport input telnet
line vty 3 4
login
transport input none
```

Category:

- ☒ Session
 - Logging
- ☐ Terminal
 - Keyboard
 - Bell
 - Features
- ☐ Window
 - Appearance
 - Behaviour
 - Translation
 - Selection
 - Colours
- ☐ Connection
 - Data
 - Proxy
 - Telnet
 - Rlogin
 - SSH
 - Serial

Basic options for your PuTTY session

Specify the destination you want to connect to

Host Name (or IP address) Port

50.0.0.1 23

Connection type:

☐ Raw
 ☒ Telnet
 ☐ Rlogin
 ☐ SSH
 ☐ Serial

Load, save or delete a stored session

Saved Sessions

Default Settings

Load

Save

Delete

Close window on exit

User Access Verification

Password:

ROUTER>

QEMU (Win)



50.0.0.1 - PuTTY

User Access Verification

Password:

ROUTER>en


Password:

ROUTER#

```
ROUTER#config t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#enab
ROUTER(config)#enable sec
ROUTER(config)#enable secret cisco
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#line con
ROUTER(config)#line console 0
ROUTER(config-line)#password cisco
ROUTER(config-line)#exit
ROUTER(config)#exit
Aug 25 08:03:38.185: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#config t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#line vty 0 2
ROUTER(config-line)#no pass
ROUTER(config-line)#no password
ROUTER(config-line)#
ROUTER(config-line)#
ROUTER(config-line)#exit
ROUTER(config)#username sakthi pa
ROUTER(config)#username sakthi password sakthi
ROUTER(config)#line vty 0 2
ROUTER(config-line)#login local
ROUTER(config-line)#

% Invalid input detected at '^' marker.

ROUTER(config-line)#
ROUTER(config-line)#
ROUTER(config-line)#
ROUTER(config-line)#login lo
ROUTER(config-line)#login local
ROUTER(config-line)#
```



QEMU (Win)



50.0.0.1 - PuTTY

User Access Verification

Username: cisco

Password:

ROUTER>