

Aug 24 14:34:05.381: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet
3, changed state to down

ROUTER#

ROUTER#en

ROUTER#config t

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#int e0/0

ROUTER(config-if)#ip add 50.0.0.1 255.0.0.0

ROUTER(config-if)#no shutdown

ROUTER(config-if)#exit

ROUTER(config)#exit

ROUTER#

*Aug 24 14:34:05.381: %SYS-5-CONFIG_I: Configured from console by console

ROUTER#exit

Administrator: Command Prompt

C:\Users\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix	:	:
Link-local IPv6 Address	:	fe80::b020:d0a:5681:8ebb%11
IPv4 Address.	:	50.0.0.10
Subnet Mask	:	255.0.0.0
Default Gateway	:	:

Tunnel adapter isatap.{42A1F8B7-30A8-4EF7-81AF-C694F5F3D81B}:

Media State	:	Media disconnected
Connection-specific DNS Suffix	:	:

Tunnel adapter 6T04 Adapter:

Connection-specific DNS Suffix	:	:
IPv6 Address.	:	2002:3200:a::3200:a
Default Gateway	:	:

C:\Users\user>

C:\Users\user>

C:\Users\user>

C:\Users\user>ping 50.0.0.1

Pinging 50.0.0.1 with 32 bytes of data:

Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Reply from 50.0.0.1: bytes=32 time<1ms TTL=255

Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Ping statistics for 50.0.0.1:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\Users\user>

Press RETURN to get started.

ROUTER#

ROUTER#

ROUTER#

ROUTER#sh ip int br

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	unassigned	YES	TFTP	down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

ROUTER#

Packets: Sent = 4, Received = 4.
Approximate round trip times in milli
Minimum = 0ms, Maximum = 1ms, Ave

C:\Users\user>

Ethernet0/3

unassigned

YES TFTP down

ROUTER#

ROUTER#config t

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#

ROUTER(config)#username sanjay password 8110067109

ROUTER(config)#line console 0

ROUTER(config-line)#login local

ROUTER(config-line)#exit

ROUTER(config)#exit

ROUTER#

*Aug 24 14:44:24.387: %SYS-5-CONFIG_I: Configured from console by console

ROUTER#

ROUTER#

ROUTER#

ROUTER#exit

Press RETURN to get started.

User Access Verification

Username: sanjay

Password:

ROUTER>

Packets: Sent = 4, R
Approximate round trip t
Minimum = 0ms, Maxim

C:\Users\user>

User Access Verification

Username: sanjay

Password:

ROUTER>

ROUTER>

ROUTER>en

ROUTER#config t

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#enable secret enable

ROUTER(config)#no enable secret enable

ROUTER(config)#line vty 0 4

ROUTER(config-line)#transport input telnet

ROUTER(config-line)#password 8110067109

ROUTER(config-line)#

Packets: Sent = 4, Received
Approximate round trip times in
Minimum = 0ms, Maximum = 1ms