




QEMU (Win)



My Documents

Local Area Connection Properties

General Advanced

Internet Protocol (TCP/IP) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address:

50 . 0 . 0 . 10

Subnet mask:

255 . 0 . 0 . 0

Default gateway:

50 . 0 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server:

Alternate DNS server:

```

Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int e0/0
Router(config-if)#ip add 172.16.0.1 255.255.0.0
Router(config-if)#no shutdown
Router(config-if)#
*Aug 29 03:46:36.598: %LINK-3-UPDOWN: Interface Ethernet0/0, changed state to up
*Aug 29 03:46:37.599: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
0, changed state to up
Router(config-if)#int e0/1
Router(config-if)#ip add 8.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
*Aug 29 03:47:15.405: %LINK-3-UPDOWN: Interface Ethernet0/1, changed state to up
*Aug 29 03:47:16.406: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
1, changed state to up
Router(config-if)#exit
Router(config)#int e0/1
Router(config-if)#ip add 8.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#int e0/2
Router(config-if)#ip add 50.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#exit
*Aug 29 03:48:48.685: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to up
*Aug 29 03:48:49.685: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
2, changed state to up
Router(config-if)#exit
Router(config)#
Router(config)#en
% Incomplete command.

Router(config)#exit
Router#
*Aug 29 03:48:59.335: %SYS-5-CONFIG_I: Configured from console by console
Router#sh ip int br

```

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	172.16.0.1	YES	manual	up	up
Ethernet0/1	8.0.0.1	YES	manual	up	up
Ethernet0/2	50.0.0.1	YES	manual	up	up
Ethernet0/3	unassigned	YES	unset	administratively down	down

```

Router#

```



SUREN NETWORK

PLAY WITH TECHNOLOGIES

172.16.0
HOTSTA



QEMU (Linux-1)




```
ENABLE=yes  
NAME=Ethernet  
IPADDRESS=172.16.0.10  
CIDRLEN=16  
NETWORK=172.16.0.0  
NETMASK=255.255.0.0  
GATEWAY=172.16.0.1  
BROADCAST=172.16.255.255  
DHCP=no
```

QEMU (Winserver)



Server Manager



Server Manager ▸ Dashboard

Dashboard

Local Server

All Servers

File and Storage S

Network Connections

Internet Protocol Version 4 (TCP/IPv4) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address:

172 . 16 . 0 . 20

Subnet mask:

255 . 255 . 0 . 0

Default gateway:

172 . 16 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server:

Alternate DNS server:

Connection

Co

s:

CP/IPv4)

ultiplexor Protocol


r

CP/IPv6)

y Responder

y Mapper I/O Drv

Prope



QEMU (DNS)



This PC DNS Manager

File Action View Help

DNS

SERVER2016

Forward Lookup Zone

com

hotstar

Reverse Lookup Zone

Trust Points

Conditional Forwarders

www Properties

Host (A)

Host (uses parent domain if left blank):

www

Fully qualified domain name (FQDN):

www.hotstar.com

IP address:


172.16.0.10


☐ Update associated pointer (PTR) record

OK

Cancel

Apply







QEMU (DNS)



Server Manager ▸ Dashboard



Network Connections



Da



Loc



All



File

Internet Protocol Version 4 (TCP/IPv4) Properties



General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address:

8 . 8 . 8 . 8

Subnet mask:

255 . 0 . 0 . 0

Default gateway:

8 . 0 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server:

.

Alternate DNS server:

.

