







```
R2 (dhcp-config) #  
R2 (dhcp-config) #  
R2 (dhcp-config) #exit  
R2 (config) #no ip dhcp pool HR  
R2 (config) #  
R2 (config) #  
R2 (config) #int e0/0  
R2 (config-if) #ip helper-address 172.16.0.1  
R2 (config-if) #exit  
R2 (config) #
```

R1

```
R1#show ip dhcp binding
Bindings from all pools not associated with VRF:
IP address          Client-ID/
                   Hardware address/
                   User name
50.0.0.51           0100.5079.6668.1f      Aug 10 2026 07:14 AM    Automatic
R1#
R1#
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#
R1(config)#
R1(config)#no ip dhcp pool SALES
R1(config)#ip dhcp pool salses
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.50
R1(config)#exit
R1#
*Aug  9 05:25:13.140: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

 VPC-4 — □ ×
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.


VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-4> ip dhcp
DDORA IP 192.168.2.52/24 GW 192.168.2.1

VPC-4> █



```
ip dhcp
VPC-4> ip dhcp
DORA IP 192.168.2.52/24 GW 192.168.2.1
VPC-4> 
```

