

PNETLab | Topology

VPC-2

Welcome to Virtual PC Simulator, version 1.3 (0.0.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.0.12/8 GW 50.0.0.1

VPC-2> █

Notifications

 **SUREN NETWORK**
PLAY WITH TECHNOLOGIES

172.16.0.1

e0/1

172.16.0.2

e0/1

R2

e0/0

192.168.2.1

Net

Win

VPC-4

HR DEPARTMENT

SALES DEPARTMENT

DHCP & RELAY

Physical

01 : 00 : 00

START

Search



ENG
IN

18:55
11-06-2026

PNETLab | Topology

VPC-2

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.0.12/8 GW 50.0.0.1
VPC-2> []
```

VPC-1

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file
```

R1

```
R1(dhcp-config)#lease 1 0 0
R1(dhcp-config)#exit
R1(config)#exit
R1#sh
*Jun 11 13:24:05.981: $SYS-5-CONFIG_I: Configured from console by console
R1#sh ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration  Type
Hardware address/
User name
R1#sh ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration  Type
Hardware address/
User name
50.0.0.11       0100.5079.6668.45  Jun 12 2026 01:24 PM Automatic
R1#sh ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration  Type
Hardware address/
User name
50.0.0.11       0100.5079.6668.45  Jun 12 2026 01:24 PM Automatic
50.0.0.12       0100.5079.6668.46  Jun 12 2026 01:25 PM Automatic
R1#
```

HR DE

2.168.2.1

Net

Win

VPC-4

Physical

01 : 00 : 00

START

DHCP & RELAY

18:56 11-06-2026

PNETLab | Topology

labs.surenetwork.com/legacy/topology

```
R1#
Hardware address/
User name
50.0.0.11      0100.5079.6668.45      Jun 12 2026 01:24 PM      Automatic
50.0.0.12      0100.5079.6668.46      Jun 12 2026 01:25 PM      Automatic
R1#
R1#
R1#
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp excluded-address 192.168.2.10 192.168.2.20
R1(config)#ip dhcp pool SALES
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 2
R1(dhcp-config)#exit
R1(config)#
R1(config)#exit
*Jun 11 13:32:38.801: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

```
R2#
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#interface e0/0
R2(config-if)#ip add 192.168.2.1 255.255.255.0
R2(config-if)#
*Jun 11 13:27:41.790: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2(config-if)#no sh
R2(config-if)#exit
R2(config)#interface e0/1
R2(config-if)#ip add 172.16.0.2 255.255.0.0
R2(config-if)#no sh
R2(config-if)#exit
R2(config)#exit
R2#
*Jun 11 13:33:13.619: %SYS-5-CONFIG_I: Configured from console by console
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#interface e0/0
R2(config-if)#ip helper-address 172.16.0.1
R2(config-if)#exit
R2(config)#exit
R2(config)#
```

HR DEPARTMENT

SALES DEPARTMENT

Physical

01 : 00 : 00 START

Rainy days ahead 31°C

Search

ENG IN

19:03 11-06-2026

