






R2



```
Router(config-if)#ex
Router(config)#
Router(config)#ip dhcp pool Sales
Router(dhcp-config)#network 192.168.2.0
Router(dhcp-config)#default-router 192.168.2.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#ip dhcp excluded-address 192.168.2.1 192.168.2.20
Router(config)#
Router(config)#ip dhcp pool HR
Router(dhcp-config)#network 50.0.0.0
Router(dhcp-config)#default-router 50.0.0.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#ip dhcp excluded-address 50.0.0.1 50.0.0.20
Router(config)#
Router(config)#ex
% Ambiguous command:  "ex"
Router(config)#exit
Router#s
*Jul 28 15:12:07.828: %SYS-5-CONFIG_I: Configured from console by console
Router#sh ip dhcp binding
Bindings from all pools not associated with VRF:
IP address          Client-ID/
                   Hardware address/
                   User name
Lease expiration
Type
```

DHCP SERVICE CONFIG FOR SALES AND HR DEPT IN R2

R1

```
R1(config-if)#no sh
R1(config-if)#
R1(config-if)#ex
R1(config)#
R1(config)#int e0/0
R1(config-if)#ex
R1(config)#
R1(config)#ip route 192.168.2.0 255.255.255.0 172.16.0.2
R1(config)#
R1(config)#int e0/0
R1(config-if)#ip helper-address 172.16.0.2
R1(config-if)#
R1(config-if)#ex
R1(config)#
```

RELAY AGENT CONFIGURATION IN R1

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.0.21/8 GW 50.0.0.1

VPC-1> █

GET IP FROM DHCP IN VPC1

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)

Dedicated to Daling.

Build time: May 7 2022 15:27:29

Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)

Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)

All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.

Source code and license can be found at vpcs.sf.net.

For more information, please visit wiki.freecode.com.cn.

Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp

DDORA IP 50.0.0.22/8 GW 50.0.0.1

VPC-2> █

GET IP FROM DHCP IN VPC2

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix	:	:
IP Address	:	192.168.2.21
Subnet Mask	:	255.255.255.0
Default Gateway	:	192.168.2.1

C:\Documents and Settings\user>_

GET IP FROM DHCP IN PC3

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)

Dedicated to Daling.

Build time: May 7 2022 15:27:29

Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)

Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)

All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.

Source code and license can be found at vpcs.sf.net.

For more information, please visit wiki.freecode.com.cn.

Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-4> ip dhcp

DDORA IP 192.168.2.22/24 GW 192.168.2.1

VPC-4> █

GET IP FROM DHCP IN VPC4