


SUBNETTING


HR


50-PC

PRODUCTION 120-PC

SALES 250-PC







 VPC-1

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.1.131/26 GW 50.0.1.129

VPC-1> █
```


```
R2

Ethernet0/2          50.0.1.197      YES manual up      up
Ethernet0/3          unassigned    YES TFTP   down      down

R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#ip route 50.0.1.128 255.255.255.192 50.0.1.193
R2(config)#ip route 50.0.0.0 255.255.255.0 50.0.1.198
R2(config)#end
R2#sh ip
*Jul 31 01:38:57.815: %SYS-5-CONFIG_I: Configured from console by console
R2#sh ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       a - application route
       + - replicated route, % - next hop override, p - overrides from Pfr

Gateway of last resort is not set

    50.0.0.0/8 is variably subnetted, 8 subnets, 5 masks
S       50.0.0.0/24 [1/0] via 50.0.1.198
C       50.0.1.0/25 is directly connected, Ethernet0/0
L       50.0.1.1/32 is directly connected, Ethernet0/0
S       50.0.1.128/26 [1/0] via 50.0.1.193
C       50.0.1.192/30 is directly connected, Ethernet0/1
L       50.0.1.194/32 is directly connected, Ethernet0/1
C       50.0.1.196/30 is directly connected, Ethernet0/2
L       50.0.1.197/32 is directly connected, Ethernet0/2
R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#int e0/0
R2(config-if)#ip helper-address 50.0.1.193
R2(config-if)#end
R2#
*Jul 31 01:41:07.600: %SYS-5-CONFIG_I: Configured from console by console
R2#
```



 VPC-2

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.1.3/25 GW 50.0.1.1


VPC-2> █
```



```

!
!
!
!
!
!
!
!
!
!
interface Ethernet0/0
 ip address 50.0.0.1 255.255.255.0
 ip helper-address 50.0.1.193
 duplex auto
!
interface Ethernet0/1
 ip address 50.0.1.198 255.255.255.252
 duplex auto
!
interface Ethernet0/2
 no ip address
 duplex auto
!
interface Ethernet0/3
 no ip address
 duplex auto
!
ip forward-protocol nd
!
!
no ip http server
no ip http secure-server
ip route 50.0.1.0 255.255.255.128 50.0.1.197
ip route 50.0.1.128 255.255.255.192 50.0.1.197
ip route 50.0.1.192 255.255.255.252 50.0.1.197
!
ipv6 ioam timestamp
!
!
!

```

 VPC-3

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-3> ip dhcp
DDORA IP 50.0.0.3/24 GW 50.0.0.1

VPC-3> █
```