




Cisco Packet Tracer

File Edit Options View Tools Extensions Window Help

Logical Physical x 947, y 409

```
graph LR
    PC3[PC-PT PC3] --- Fa0_0[Fa0/0] --- Router1[2621XM Router1]
    Router1 --- Fa0_1[Fa0/1] --- PC4[PC-PT PC4]
    Router1 --- Fa0 --- PC5[PC-PT PC5]
```

Time: 07:57:13

PC3

Physical Config Desktop Programming Attributes

terminal

```
User Access Verification
Username: sathish
Password:
* Login Invalid

Username:
Username: sathish
Password:

Router#enable
Password:
Router#configure terminal
% Invalid input detected at '^' marker.

Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#line vty 0 4
Router(config-line)#transport input telnet
Router(config-line)#password 1230
Router(config-line)#login
Router(config-line)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#exit

Router con0 is now available
```

Simulation

```

PC3
Physical Config Desktop Programming Attributes

Terminal

User Access Verification

Username: sathishah
Password:
% Login invalid

Username: sathish
Password:

Router>enable
Password:
Router>configure terminal
Router(config)#line vty 0 4
Router(config-line)#transport input telnet
Router(config-line)#password 1230
Router(config-line)#login
Router(config-line)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#exit

Router con0 is now available
    
```

```

PC4
Physical Config Desktop Programming Attributes

Command Prompt

Bluetooth Connection:

Connection-specific DNS Suffix...:
Link-local IPv6 Address . . . . .: ::
IPv6 Address . . . . .: ::
IPv4 Address . . . . .: 0.0.0.0
Subnet Mask . . . . .: 0.0.0.0
Default Gateway . . . . .: ::

C:\>ipconfig

FastEthernet0 Connection (default port):

Connection-specific DNS Suffix...:
Link-local IPv6 Address . . . . .: FE80::801:42FF:FE56:4B59
IPv6 Address . . . . .: ::
IPv4 Address . . . . .: 50.0.0.10
Subnet Mask . . . . .: 255.0.0.0
Default Gateway . . . . .: ::

Bluetooth Connection:

Connection-specific DNS Suffix...:
Link-local IPv6 Address . . . . .: ::
IPv6 Address . . . . .: ::
IPv4 Address . . . . .: 0.0.0.0
Subnet Mask . . . . .: 0.0.0.0
Default Gateway . . . . .: ::

C:\>ping 50.0.0.1

Pinging 50.0.0.1 with 32 bytes of data:

Reply from 50.0.0.1: bytes=32 time=1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Ping statistics for 50.0.0.1:
    Packets: Sent = 4, Received = 4, Loss = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms
    
```

```
PCS
Pinging 60.0.0.1 with 32 bytes of data:
Reply from 60.0.0.1: bytes=32 time=1ms TTL=255
Reply from 60.0.0.1: bytes=32 time=1ms TTL=255
Reply from 60.0.0.1: bytes=32 time=1ms TTL=255
Reply from 60.0.0.1: bytes=32 time=1ms TTL=255

Ping statistics for 60.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>telnet 60.0.0.1
Trying 60.0.0.1 ...Open

User Access Verification

Password:
Router>enable
Router>configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
```

Top

```
PC4
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>telnet 60.0.0.1
Trying 60.0.0.1 ...Open

User Access Verification

Password:
Router>enable
Router>configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#

Router>
Router>enable
Password:
Router>show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 50.0.0.1        YES manual up          up
FastEthernet0/1 60.0.0.1        YES manual up          up
Router#

[Connection to 60.0.0.1 closed by foreign host]
C:\>
```

Top

```
PC3
User Access Verification

Username: sathish
Password:

Router>enable
Router>show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 50.0.0.1        YES manual up          up
FastEthernet0/1 60.0.0.1        YES manual up          up
Router#ping 50.0.0.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 50.0.0.10, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/0 ms

Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#

Router>enable
Router>configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
```

Top

