IBO Lite

IBO Lite Player

UX Scenario

How the app works on an LG TV: every screen, every key, and what to test.

App ID	com.iboliteplayer.tv
App version	2.0.37
Platform	webOS TV 4.0 (2018) and later · Web app
Packages	1920×1080 (UHD TVs) and 1280×720 (FHD TVs)
Remote	Magic Remote (pointer, wheel) and standard remote
Language	English
Website	ibolite.pro
Date	16 October 2026

OVERVIEW

About the app and how to test it

WHAT THE APP IS

- IBO Lite Player is a **media player**. It contains no channels, films or other content and sells none.
- Users add their **own playlist** (an M3U link or an Xtream Codes login) on the website **ibolite.pro** by scanning the QR code shown on the TV. Nothing has to be typed on the TV.
- A **built-in demo** (free open films from the Blender Foundation under Creative Commons, and public test streams) lets anyone try the player without a playlist.
- Live TV with a preview window and programme guide, Movies and TV Series with covers and details, Catch Up for Xtream playlists that offer it, search, favourites, recently watched and resume.

QUICK TEST PATH


1. Start the app. On the first screen **Watch the 4K demo** has the focus: press **OK**.
2. Home: open **Live TV**, pick a channel (OK = preview, OK again = full screen).
3. Back to Home, open **Movies**, a film, then **Watch now**.
4. Open **TV Series**, a series, then an episode.

TEST INFORMATION

Login / test account	Not needed. The app has no sign-in or membership.
In-app purchase	None. The app starts with a free trial. After the trial a licence is bought on the website (card payment there); the TV only shows an activation screen with a QR code and an activation-code field (last page).
In-app advertising	None.
Adult content	None in the app.
Sound	No background music or sound effects; sound comes only from the video being played.
Keyboard	Search and the activation-code field use the TV's own on-screen keyboard.
Network	An internet connection is needed (wired or Wi-Fi).
Back on the first screen	The app hands over to the TV (webOS platformBack): Home screen / launcher.
Data	The TV's MAC address links it to the playlists added on the website. Favourites, history and settings stay on the TV.

NAVIGATION

Screen map



Back goes one step back along these arrows and closes any open window. On the first screen (Start screen, Home or Activation) Back hands over to the TV.

KEYS

Remote control

STANDARD REMOTE

KEY	SCREENS AND LISTS	PLAYER
Arrows	Move the focus	Live: Up / Down next / previous channel, Left channel list, Right options. Film: Left / Right jump back / forward, Down shows the buttons.
OK	Open / select	Shows the information bar and buttons
Hold OK	On a channel or title: add to / remove from Favourites. On a category: move it (Up / Down, then OK).	–
BACK	One step back; closes windows. First screen: the TV takes over.	Hides the bar, then leaves the player
CH + / CH –	Page up / down in long lists	Live: next / previous channel
0 – 9	–	Live: type a channel number
Media keys	FF / REW page through lists	Film: Play, Pause, Stop (leave), FF / REW jump forward / back
INFO	–	Live: information bar
HOME / EXIT	Handled by the TV (launcher / app closes)	

MAGIC REMOTE


- **Pointer:** pointing at an item focuses it (the same red frame as with the arrow keys).
- **Click (OK):** opens / selects the item under the pointer.
- **Wheel:** scrolls lists and grids in the same direction as the wheel.
- **BACK, HOME:** as on the standard remote.
- Favourites can also be set with the **Favourite** buttons (film details, next to the live preview).
- When the pointer is hidden, the arrow keys move the focus again.

NOT USED

- Colour keys have no function on screen.
  - Support only: pressing the red key five times quickly shows a small technical log; five times again hides it.

SCREEN 1

Start screen: Add your playlist



ON THIS SCREEN


- Shown when the TV has no playlist yet.
- QR code, this TV's **MAC Address** and **Device Key**.
- Steps: scan the QR code with a phone (or open ibolite.pro/upload-playlist) and add an M3U link or Xtream Codes login. The playlist appears on the TV by itself ("Waiting for your playlist...").
- **Watch the 4K demo** (focused) opens the built-in demo.

KEYS

OK	Watch the 4K demo → Home with the demo
BACK	The TV takes over (first screen)

SCREEN 2

Home



ON THIS SCREEN

- Top bar: **playlist button** (shows its name, opens the Playlists window), **Settings**, and three icons: **Update playlist**, **My device** (MAC, Device Key, QR), **Account** (playlist type, status, expiry).
- Tiles: **Live TV, Movies, TV Series, Catch Up**.
- Information: MAC Address, Device Key, application expiry (free trial or licence), date, time and weather.


KEYS

Arrows / OK	Move / open
BACK	The TV takes over (first screen)


> Catch Up needs an Xtream Codes playlist with recordings; with the demo it shows a short message.

SCREEN 2 · WINDOWS

Playlists window and streaming boxes




Playlists (playlist button): choose between the playlists added on the website and the built-in demo. Close or BACK closes it.



Streaming boxes (chosen in Settings) appear under the tiles: each opens the films and series of the user's own playlist that are on that service. Only the service name is shown, no logos.

SCREEN 3

Live TV



ON THIS SCREEN


- Left: categories (Search, All, Favourites, Recent, then the playlist's categories).
- Middle: channels of the category.
- Right: preview window with programme guide (now / next), and buttons Full screen, Favourite, Search.

KEYS

OK	Plays the channel in the preview; OK again → full screen
Hold OK	Favourite on / off (channel), move (category)
CH + / –	Page through the list
BACK	Home

SCREEN 4

Live TV: full screen



ON THIS SCREEN


- Information bar: channel number and name, picture size, playlist, time, current programme with progress, next programme.
- Buttons: channel list, previous / next channel, audio track, favourite, back.
- If a stream stops, the player reconnects by itself.

KEYS

Up / Down, CH ±	Next / previous channel
0 – 9	Channel number
Left / Right	Channel list / options
OK, INFO	Information bar
BACK	Hides the bar, then back to the list

SCREEN 5

Movies



ON THIS SCREEN


- Left: categories (Search, All Movies, Favourites, Recent, then the playlist's categories). The number of titles is shown at the top.
- Right: covers with title and year.

KEYS


OK	Film details
Hold OK	Favourite on / off (title), move (category)
Wheel / CH ±	Scroll / page
BACK	Home

SCREEN 5 · SEARCH

Search



Search (top of the category list, or the Search button) opens a field; the TV's on-screen keyboard opens with it. OK or the Search button starts the search; Cancel or BACK closes it.



Results appear as a category "Search: ...". Every word is matched; case, accents and dashes are ignored.

SCREEN 6

Film details



ON THIS SCREEN


- Cover picture, title, rating, length, year, country, genres, description, director and cast (when the playlist has them).
- **Watch now** (or **Resume from mm:ss** after a film was stopped) and **Favourite**.

KEYS

OK	Watch now / Favourite
BACK	Back to the list

SCREEN 7

Film player



ON THIS SCREEN

- Title and year, picture size, playlist and time at the top.
- Progress bar with time; buttons: jump back, play / pause, jump forward, audio track, back.
- The place where a film is stopped is kept, so the next time it can resume.


KEYS

Left / Right	Jump back / forward
Down	The buttons
Media keys	Play, Pause, Stop (leave), FF / REW jump
BACK	Hides the bar, then back to the details

> The picture in this screenshot is a test pattern used for the screenshot only.

SCREEN 8

TV Series



ON THIS SCREEN


- Series cover and description on the left.
- Season buttons at the top, episodes with length below; a marker shows episodes already started.

KEYS

Arrows	Seasons (top) and episodes (below)
OK	Plays the episode (same player as films)
BACK	Back to the list

SCREEN 9

Favourites and the order of categories



ON THIS SCREEN


- Holding OK on a channel or title adds it to **Favourites** (holding again removes it).
- Holding OK on a **category** picks it up: Up / Down move it, OK places it. The order is kept on the TV.

KEYS

Hold OK	Pick up a category
Up / Down	Move it
OK or BACK	Place it (the order is saved)

SCREEN 10

Settings



ON THIS SCREEN


- Left: app name, version and licence status (e.g. "Free trial · 87 days left").
- Playlists · Live stream format (Automatic / HLS / MPEG-TS) · My device · Account · Streaming boxes · Clear watch history (asks first) · Restart the app.

KEYS


OK	Open / change the setting
BACK	Home

SCREEN 10 · WINDOW

Streaming boxes




Settings → Streaming boxes: switch services on or off (Netflix, Prime Video, Disney+, HBO Max, Apple TV+, Paramount+, Hulu, Peacock). Close or BACK closes it.



The chosen services appear as boxes on Home. The lists come from the website; the films themselves come only from the user's own playlist.

SCREEN 11

Activation (after the free trial)



ON THIS SCREEN

- Shown instead of Home when the free trial or the licence has ended.
- QR code and MAC Address: scanning opens ibolite.pro/activation, where the user buys a licence (card payment on the website, not in the app) and gets an activation code.
- The code is entered in the field with the TV's keyboard; **Activate** checks it. When the licence is renewed on the website, the TV notices it by itself.

KEYS

OK	Opens the keyboard / Activate
BACK	The TV takes over (first screen)

> Testers do not reach this screen: every new TV starts with a free trial.