JavaScript is disabled on your browser.

Java SE 27 & JDK 27

Interface ClassLoadingMXBean

All Superinterfaces:

`PlatformManagedObject`

```
public interface ClassLoadingMXBean
extends PlatformManagedObject
```

The management interface for the class loading system of the Java virtual machine.

A Java virtual machine has a single instance of the implementation class of this interface. This instance implementing this interface is an MXBean that can be obtained by calling the `ManagementFactory.getClassLoadingMXBean()` method or from the `platform MBeanServer`.

The `ObjectName` for uniquely identifying the MXBean for the class loading system within an `MBeanServer` is:

```
java.lang:type=ClassLoading
```

It can be obtained by calling the `PlatformManagedObject.getObjectName()` method.

Since:

1.5

See Also:

`ManagementFactory.getPlatformMXBeans(Class)`,
JMX Specification.,
Ways to Access MXBeans

Method Summary

All Methods	Instance Methods	

Modifier and Type	Method	Description
`int`	**`getLoadedClassCount`**`()`	Returns the number of classes that are currently loaded in the Java virtual machine.
`long`	**`getTotalLoadedClassCount`**	Returns the total number of classes that have been loaded since the Java virtual machine has started execution.

long	**getUnloadedClassCount**()	Returns the total number of classes unloaded since the Java virtual machine has started execution.
boolean	**isVerbose**()	Tests if the verbose output for the class loading system is enabled.
void	**setVerbose** (boolean value)	Enables or disables the verbose output for the class loading system.

Methods declared in interface PlatformManagedObject

getObjectName

Method Details

getTotalLoadedClassCount

```
long getTotalLoadedClassCount()
```

Returns the total number of classes that have been loaded since the Java virtual machine has started execution.

Returns:

the total number of classes loaded.

getLoadedClassCount

```
int getLoadedClassCount()
```

Returns the number of classes that are currently loaded in the Java virtual machine.

Returns:

the number of currently loaded classes.

getUnloadedClassCount

```
long getUnloadedClassCount()
```

Returns the total number of classes unloaded since the Java virtual machine has started execution.

Returns:

the total number of unloaded classes.

isVerbose

```
boolean isVerbose()
```

Tests if the verbose output for the class loading system is enabled.

Returns:

`true` if the verbose output for the class loading system is enabled; `false` otherwise.

setVerbose

```
void setVerbose(boolean value)
```

Enables or disables the verbose output for the class loading system. The verbose output information and the output stream to which the verbose information is emitted are implementation dependent. Typically, a Java virtual machine implementation prints a message each time a class file is loaded.

This method can be called by multiple threads concurrently. Each invocation of this method enables or disables the verbose output globally.

Parameters:

`value` - `true` to enable the verbose output; `false` to disable.

Report a bug or suggest an enhancement
For further API reference and developer documentation see the Java SE Documentation, which contains more detailed, developer-targeted descriptions with conceptual overviews, definitions of terms, workarounds, and working code examples. Other versions.
Java is a trademark or registered trademark of Oracle and/or its affiliates in the US and other countries.
Copyright © 1993, 2026, Oracle and/or its affiliates, 500 Oracle Parkway, Redwood Shores, CA 94065 USA.
All rights reserved. Use is subject to license terms and the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.