JavaScript is disabled on your browser.

compact1, compact2, compact3

java.util.logging

Class ErrorManager

java.lang.Object
    java.util.logging.ErrorManager

```
public class ErrorManager
extends Object
```

ErrorManager objects can be attached to Handlers to process any error that occurs on a Handler during Logging.

When processing logging output, if a Handler encounters problems then rather than throwing an Exception back to the issuer of the logging call (who is unlikely to be interested) the Handler should call its associated ErrorManager.

Field Summary

Fields

Modifier and Type	Field	Description
static int	CLOSE_FAILURE	CLOSE_FAILURE is used when a close of an output stream fails.
static int	FLUSH_FAILURE	FLUSH_FAILURE is used when a flush to an output stream fails.
static int	FORMAT_FAILURE	FORMAT_FAILURE is used when formatting fails for any reason.
static int	GENERIC_FAILURE	GENERIC_FAILURE is used for failure that don't fit into one of the other categories.

static int	**OPEN_FAILURE**	OPEN_FAILURE is used when an open of an output stream fails.
static int	**WRITE_FAILURE**	WRITE_FAILURE is used when a write to an output stream fails.

Constructor Summary

Constructors

Constructor	Description
ErrorManager()	

Method Summary

Concrete Methods

Modifier and Type	Method	Description
void	**error**(**String** msg, **Exception** ex, int code)	The error method is called when a Handler failure occurs.

Methods inherited from class java.lang.Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, toString, wait, wait, wait

Field Detail

GENERIC_FAILURE

```
public static final int GENERIC_FAILURE
```

GENERIC_FAILURE is used for failure that don't fit into one of the other categories.

See Also:

Constant Field Values

WRITE_FAILURE

```
public static final int WRITE_FAILURE
```

WRITE_FAILURE is used when a write to an output stream fails.

See Also:

Constant Field Values

FLUSH_FAILURE

```
public static final int FLUSH_FAILURE
```

FLUSH_FAILURE is used when a flush to an output stream fails.

See Also:

Constant Field Values

CLOSE_FAILURE

```
public static final int CLOSE_FAILURE
```

CLOSE_FAILURE is used when a close of an output stream fails.

See Also:

Constant Field Values

OPEN_FAILURE

```
public static final int OPEN_FAILURE
```

OPEN_FAILURE is used when an open of an output stream fails.

See Also:

Constant Field Values

FORMAT_FAILURE

```
public static final int FORMAT_FAILURE
```

FORMAT_FAILURE is used when formatting fails for any reason.

See Also:

Constant Field Values

Constructor Detail

ErrorManager

```
public ErrorManager()
```

Method Detail

error

```
public void error(String msg,
                  Exception ex,
                  int code)
```

The error method is called when a Handler failure occurs.

This method may be overridden in subclasses. The default behavior in this base class is that the first call is reported to System.err, and subsequent calls are ignored.

Parameters:

`msg - a descriptive string (may be null)`

`ex - an exception (may be null)`

`code - an error code defined in ErrorManager`

Submit a bug or feature
For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.
Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.